

General Disclaimer

One or more of the Following Statements may affect this Document

- This document has been reproduced from the best copy furnished by the organizational source. It is being released in the interest of making available as much information as possible.
- This document may contain data, which exceeds the sheet parameters. It was furnished in this condition by the organizational source and is the best copy available.
- This document may contain tone-on-tone or color graphs, charts and/or pictures, which have been reproduced in black and white.
- This document is paginated as submitted by the original source.
- Portions of this document are not fully legible due to the historical nature of some of the material. However, it is the best reproduction available from the original submission.

JUL 29 1981

AgRISTARS

"Made available under NASA sponsorship
in the interest of early and wide dis-
semination of Earth Resources Survey
Program information and without liability
for use made thereof."

SR-L1-00304
JSC-17369

NASA-CR-161067

A Joint Program for
Agriculture and
Resources Inventory
Surveys Through
Aerospace
Remote Sensing

Supporting Research

June 1981

"AS-BUILT" DESIGN SPECIFICATION FOR THE CLASFYG PROGRAM

E82-10092

C. L. Horton

(E82-10092) AS-BUILT DESIGN SPECIFICATION
FOR THE CLASFYG PROGRAM (Lockheed
Engineering and Management) 129 p
HC A07/MF A01

N82-21644

CSCL 02C

Unclas
G3/43 00092

Lockheed Engineering and Management Services Company, Inc.
1830 NASA Road 1, Houston, Texas 77058



Lyndon B. Johnson Space Center
Houston, Texas 77058


SR-L1-00304
JSC-17369


"AS-BUILT" DESIGN SPECIFICATION
FOR THE
CLASFYG PROGRAM


Job Order 71-308


Prepared By
C. L. Horton

Approved By


G. L. Clouette, Supervisor
Support Systems Software Section


R. A. McClane, Manager
Data Systems Department


R. Kent Lennington, Supervisor
Techniques Development Section


T. C. Minter, Manager
Development and Evaluation Department

Prepared By
Lockheed Engineering and Management Services Company, Inc.

For
Earth Observations Division
Space and Life Sciences Directorate
NATIONAL AERONAUTICS AND SPACE ADMINISTRATION
LYNDON B. JOHNSON SPACE CENTER
HOUSTON, TEXAS

June 1981

LEMSCO-16649

1. Report No. JSC-17369, SR-L1-00304		2. Government Accession No.		3. Recipient's Catalog No.	
4. Title and Subtitle "As-Built" Design Specification for the CLASFYG Program				5. Report Date June 1981	
				6. Performing Organization Code SG3	
7. Author(s) C. L. Horton Lockheed Engineering and Management Services Company, Inc.				8. Performing Organization Report No. LEMSCO-16649	
				10. Work Unit No. 63-2457-1308	
9. Performing Organization Name and Address Lockheed Engineering and Management Services Company, Inc. 1830 NASA Road 1 Houston, Texas 77058				11. Contract or Grant No. NAS 9-15800	
				13. Type of Report and Period Covered Design Specification	
12. Sponsoring Agency Name and Address National Aeronautics and Space Administration Lyndon B. Johnson Space Center Houston, Texas 77058 <i>Dr. G. Badhwar / SG3</i>				14. Sponsoring Agency Code 626-48	
15. Supplementary Notes					
16. Abstract This document is the "As-Built" Design Specification for the CLASFYG program. The program produces a file with a Universal-formatted header and data records in a non-standard format. Trajectory coefficients are calculated from 5 to 8 acquisitions of radiance values in the training field corresponding to an agricultural product. These coefficients are used to calculate a time of emergence and corresponding trajectory coefficients for each pixel in the test field. The time of emergence, two of the coefficients and the sigma value for each pixel are written to the file.					
17. Key Words (Suggested by Author(s)) Universal-format Trajectory coefficients Classification				18. Distribution Statement	
19. Security Classif. (of this report) Unclassified		20. Security Classif. (of this page) Unclassified		21. No. of Pages 129	
				22. Price*	

PRECEDING PAGE BLANK NOT FILMED

CONTENTS

Section	Page
1. SCOPE	1-1
2. APPLICABLE DOCUMENTS	2-1
3. SYSTEM DESCRIPTIONS	3-1
3.1 <u>SYSTEM FLOWCHART</u>	3-1
3.2 <u>HARDWARE DESCRIPTION</u>	3-1
*3.3 <u>SOFTWARE DESCRIPTION</u>	3-4
3.4 <u>FILE DESCRIPTION</u>	3-5
3.4.1 USER INFORMATION FILE	3-5
3.4.2 ACQUISITION DATA FILES	3-7
3.4.3 DATA FROM RT&E DATA BASE	3-8
3.4.4 COEFFICIENTS FILE	3-9
3.5 <u>DETAILED SOFTWARE DESCRIPTION</u>	3-11
3.5.1 CLASFG	3-11
3.5.2 CROPG	3-14
3.5.3 MOVSYM	3-16
3.5.4 NUMBFL	3-18
3.5.5 RDEXEC	3-20
3.5.6 RDFLES	3-22
3.5.7 RDVERT	3-25
3.5.8 RECT	3-27
3.5.9 SDEV	3-29
3.5.10 TRJXM	3-31
3.5.11 F2ERVG	3-34

CONTENTS

Section	Page
3.5.12 FCHISQ	3-36
3.5.13 F2NCTG	3-38
3.5.14 MTINV1	3-40
3.5.15 NUMBR	3-42
4. OPERATION INSTRUCTION	4-1
4.1 <u>OPERATING DESCRIPTION</u>	4-1
4.2 <u>COMMANDS DESCRIPTION</u>	4-2
4.2.1 START	4-3
4.2.2 CLASFYG	4-4
4.2.3 END	4-5
4.3 <u>OPERATING EXAMPLE</u>	4-6
 Appendices	
A. COMMON BLOCKS	A-1
B. CLASFYG CONSTANT DEFINITION	B-1
C. JOB CONTROL SOFTWARE	C-1
D. PROGRAM LISTINGS.	D-1
E. OUTPUT EXAMPLE	E-1

CLASFYG PROGRAM

1.0 SCOPE

This document contains the description of the CLASFYG computer program. The program calculates coefficients to fit the model

$$G(t) = A \left(\frac{t}{t_0} \right)^\alpha e^{-\beta(t_0^2 - t^2)} \text{ for } t \geq t_0$$

and

$$G(t) = A \quad \text{for } t \leq t_0$$

where G is the greenness and A is the soil line, to the time trajectory of each pixel in a specified region of a segment. A disk file is written with a Universally formatted header record and line records recording the α , β , t_0 and CHI-Square value for each pixel on the scan line.

2.0 APPLICABLE DOCUMENTS

The following documents form a part of this specification: AD 63-2457-3308-01
Transferring of Badhwar Software.

AD NAS 9-15200 Technical Memorandum Format Specifications for LACIE
(Phase III) and Accuracy Assessment Computer Data Products.

3.0 SYSTEM DESCRIPTION

3.1 HARDWARE DESCRIPTION

The software for CLASFYG is operational on the IBM 3031 computer at Purdue.

3.2 CLASFYG PROCESSOR SYSTEM FLOWCHART

The system level data flow diagram is shown in figure 3.1.

The following system flowchart assumes the use of the EXEC file described in Appendix C.

Acquisition data files (5-8)
on multifile tape(s)





Figure 3.1

ORIGINAL PAGE IS
OF POOR QUALITY

The inputs and outputs shown on Figure 3.1 are described briefly here.
A more detailed description is given in section 3.4.

- Acquisition data files - Header record and 4 channels of data for each of 5 to 8 acquisitions (See Section 3.4.3).
- User information file - User information file supplying crop, initial guesses for greenness values, training field vertices and optional test field vertices (See Section 3.4.1).
- Data from RT&E data base file - Segment number, number of acquisitions, Landsat numbers and sun angles (See Section 3.4.2).
- Summary Report - Report of date and time of processing, crop vertices for training field, acquisition dates, all statistical data created by CLASFYG and time taken to execute the program.
- Coefficients File - File of one header and 117 data records, each data record containing the Alpha, Beta, t_0 and CHI square values for each of the 196 pixels in a line of acquisition data (See Section 3.4.4).

CLASFYG Hierarchy Diagram



* Parentheses enclose the name of the file which contains the source statements for the named program which precedes them. For example,

PROGRAM (Source statement file name)

3.3 SOFTWARE DESCRIPTION

The CLASFYG program fits a model to the time trajectory of each pixel in a specified region of a segment (usually this region is the whole segment). The time trajectory consists of a plot of the greenness values for a particular pixel on various acquisitions as a function of time. The model is given by

$$G(t) = A \left(\frac{t}{t_0} \right)^\alpha e^{-\beta(t_0^2 - t^2)} \quad \text{for } t \geq t_0$$

and

$$G(t) = A \quad \text{for } t \leq t_0$$

where G is the greenness and A is the "soil line". The CLASFYG program produces estimates of the parameters A , α , β and t_0 for each pixel which give the best fit to the trajectory defined by the data for that pixel. It also calculates a value for χ^2 which describes the goodness of fit.

The first stage of the processing consists of determining starting values for A , α , β and t_0 which are subsequently used as starting points for fitting the model to pixels in the test area.

These starting values are determined using the data in a training field selected by the user and a set of initial "guesses" for these parameters also input by the user. The training field should be a field of the crop of major interest. Also during this first stage, an array $SGMX$ is calculated which contains the standard deviations of the pixels in the training field for each acquisition used. These are used in weighting the acquisitions when fitting the model to the pixels in the test area.

The second stage of the processing consists of fitting the model to each pixel in the test area starting the iteration procedure for each pixel with the starting values calculated in phase I. When this is completed the final values for α , β , t_0 and χ^2 for each pixel are output as a formatted disc file. Also a summary report is printed on the line printer.

3.4 FILE DESCRIPTION

3.4.1 USER INFORMATION FILE (Segment number) USERG A

The following records describe the name of the crop, the initial guesses for the coefficients for greenness and the training and test fields and allows the user to input any number of free-form comments.

In record types 1-5 the "keyword" is in columns 1-4 and any parameter or comment data is in columns 11 through 72. Numbers in a series are separated by commas; blanks are optional.

Record types 6 and 7 which describe the fields are blank in columns 1 through 10 and the field definition is in columns 11-72.

Record type 6 must follow the "*END" record and must precede record type 7.

Record type 7 is optional, but if it exists it must follow record type 6.

1. "COMMENT" record

EXAMPLE: COMMENT THIS IS AN EXAMPLE EXECUTION OF THE PROGRAM

These records allow the user to enter any number of free-form comments.

2. "CROP" record

EXAMPLE: CROP CORN

This record specifies the 4 character name of the crop of interest.

The name begins at the first non-blank character.

3. "GREENNESS" record

EXAMPLE: GREENNESS 12.00, 11.50, 1.50, 1.50

This record specifies the initial guesses for the A, Alpha, Beta and t_0 values of the crop in the training field.

4. "SUNANGLE" record

EXAMPLE: SUNANGLE 45, 47, 51, 46, 42

This record specifies the sun angles and is used only if the sun angles in the data base are wrong.

5. "*END" record

This record specifies the end of the user information except for the definition of the training field and test field.

6. "TRAINING FIELD" record

EXAMPLE: (1,1), (97,100), (97,120), (125,110), (100,100)

This record specifies the coordinates of the corners of the training field. The format of the line is as follows:

(1, 1) Dummy variable to be used for sample skip factor and line skip factor; not currently used.

(X₁, Y₁) Upper leftmost corner of training field expressed as (sample, line).

(X₂, Y₂) Upper rightmost corner of training field expressed as (sample, line).

(X₃, Y₃) Lower rightmost corner of training field expressed as (sample, line).

(X₄, Y₄) Lower leftmost corner of training field expressed as (sample, line).

7. "TEST FIELD" record

EXAMPLE (1,1), (1,1), (196,1), (196,117), (1,117)

This optional record specifies the coordinates of the corners of the test field. The default is the whole segment. The format is the same as the format for the training field record.

2 ACQUISITION DATA FILES

The following records of the 5 to 8 acquisitions data files are input to the ASFYG program and are read by RDFLES.

These files each contain 4 channels of LANDSAT data for one acquisition.

For each acquisition is used twice the corresponding file will be duplicated.

Note that these files are all in universal format. Record 1 is read with 17(180A1) format statement; records 2-118 are read with a 5(180A1) format statement.

<u>Record</u>	<u>Bytes</u>	<u>Contents</u>
	1-3060	Header record in universal format.
2	1-72	Filler.
	73-268	Gray level values for the 196 samples of band 1 for line 1.
	269-464	Gray level values for the 196 samples of band 2 for line 1.
	465-660	Gray level values for the 196 samples of band 3 for line 1.
	661-856	Gray level values for the 196 samples of band 4 for line 1.
3	1-856	Same data format as record 2; gray level values for bands 1-4 for line 2.
⋮		
N	1-856	Same data format as record 2; gray level values for bands 1-4 for line N-1.
⋮		
118	1-856	Same data format as record 2; gray level values for bands 1-4 for line 117.

3.4.3 DATA FROM RT&E DATA BASE

LANOSUN FILE D

The following records describe the segment number, the number of acquisitions, and the date, sun angle and Landsat numbers for each acquisition.

<u>Record</u>	<u>Bytes</u>	<u>Format</u>	<u>Contents</u>
1	1-4	A4	Segment number.
2	1-4	I4	Number of acquisitions.
3	1-56	8(2X,A5)	Acquisition dates.
4	1-32	8I4	Sun angles.
5	1-32	8I4	Landsat numbers.

3.4.4 COEFFICIENTS FILE

(Segment number) COEF A

The following records are output from the CLASFYG program:

Format

<u>Record</u>	<u>Bytes</u>	<u>Format</u>	<u>Contents</u>
1	1-3060	17(180A1)	Header record in Universal format.
2-118	3136	18(45A4)	Coefficients Alpha, Beta, t_0 and CHI-square for the 196 pixels on 1 line.

Detailed format

<u>Record</u>	<u>Words</u>	<u>Contents</u>
1	1-765	Header record in Universal format.
2	1	Alpha value for pixel 1 in line 1 (computational integer).
2	2	Beta value for pixel 1 in line 1 (computational integer).
	3	t_0 value for pixel 1 in line 1 (computational integer).
	4	CHI-square value for pixel 1 in line 1 (computational integer).
	:	
	1+N*4	Alpha value for pixel N+1 in line 1 (computational integer).
	2+N*4	Beta value for pixel N+1 in line 1 (computational integer).
	3+N*4	t_0 value for pixel N+1 in line 1 (computational integer).
	4+N*4	CHI-square value for pixel N+1 in line 1 (computational integer).
	:	
2	781	Alpha value for pixel 196 in line 1 (computational integer).
	782	Beta value for pixel 196 in line 1 (computational integer).
	783	t_0 value for pixel 196 in line 1 (computational integer).
	784	CHI-square value for pixel 196 in line 1 (computational integer).

Coefficients file (continued)

<u>Record</u>	<u>Words</u>	<u>Contents</u>
3	1-784	Same data format as record 2; Alpha, Beta, t_0 and CHI-square values for 196 pixels of line 2.
:		
M+1	1-784	Same data format as record 2; Alpha, Beta, t_0 and CHI-square values for 196 pixels of line M.
:		
118	1-784	Same data format as record 2; Alpha, Beta, t_0 and CHI-square values for 196 pixels of line 117.

3.5 DETAILED SOFTWARE DESCRIPTION

3.5.1 CLASFYG

Purpose

CLASFYG uses a user determined training field in a full scene to determine trajectory coefficients for each band of radiance values to fit the model defined in section 1.0. These coefficients Alpha, Beta, t_0 and CHI-square are written for each pixel to the output file described in section 3.4.3.

Linkages

CLASFYG calls CROPG, RDEXEC, CPTIME, RECT, SDEV, TRJXM and RDFLES.

Interface

Calling sequence:

Not applicable (an EXEC that can be used to call CLASFYG is described in Section 4.0).

Calling sequence parameters:

Not applicable.

Labeled COMMON parameters:

Full description of labeled COMMON blocks are contained in Appendix A.

<u>Label</u>	<u>Variable</u>	<u>Element Position</u>	<u>Input/ Output</u>	<u>Description</u>
/LINES/	LINENO	2	Ø	Line number.
/LINES/	IDATA(856,8)	3	I	Radiance values for a maximum of 8 channels.
/LINES/	NOACQS	4	Ø	Number of acquisitions.
/MISC/	NOACQ	1	I	Number of acquisitions.
/MISC/	ACQDT(8)	2	I	Acquisition dates.
/MISC/	KSEGM	3	I	Segment number.
/USER/	ICROP(4)	1	I	Name of crop.
/USER/	ZX(4)	2	I	Initial guesses for coefficients A, Alpha, Beta and t_0 .
/USER/	SANGGG(8)	3	Ø	Sun angle correction factor.

Blank COMMON parameters:

None.

Inputs

<u>Unit</u>	<u>Type</u>	<u>Description</u>
7	Seq. data	Data from RT&E data base (See Section 3.4.3).
11	Seq. data	Acquisition data (See Section 3.4.2).
12	Seq. data	Acquisition data (See Section 3.4.2).
13	Seq. data	Acquisition data (See Section 3.4.2).
14	Seq. data	Acquisition data (See Section 3.4.2).
15	Seq. data	Acquisition data (See Section 3.4.2).
16	Seq. data	Acquisition data (See Section 3.4.2) optional.
17	Seq. data	Acquisition data (See Section 3.4.2) optional.
18	Seq. data	Acquisition data (See Section 3.4.2) optional.
21	Seq. data	User defined parameters (See Section 3.4.1).
30	Seq. data	Scratch file to reformat data.

Outputs

<u>Unit</u>	<u>Type</u>	<u>Description</u>
6	Report	Summary report.
8	Seq. data	Header and coefficients Alpha, Beta, t_0 and CHI-square.
30	Seq. data	Scratch file to reformat data.

Storage requirement

Not applicable.

Description

CLASFYG calls CROPG to read the user specified parameters crop of interest and initial guesses for greenness coefficients A, Alpha, Beta, t_0 .

CLASFYG calls RDFLES to read the header record and the parameters for the training field.

CLASFYG then calls CPTIME to get the current time and date and writes the report heading.

CLASFYG calculates the minimum and maximum boundaries for pixels in the test field, calculates days elapsed from the beginning of the year as a multiple of 100 for each acquisition date and sets a switch if an acquisition date is used twice.

The rectangular field bounded by the minimum and maximum pixel numbers and line numbers is then processed using the following steps:

A line of radiance values is read.

Each pixel in the field is checked to be in the training field.

The values for the pixels in the training fields are used to calculate a greenness value which is saved in a matrix.

When sufficient pixels have been accumulated, the mean and standard deviation are calculated for the test field.

CLASFYG calls TRJXM to calculate improved values for A, Alpha, Beta and t_0 and a CHI-square value for the training field.

The header record is constructed from constants in the program, input from the user parameter file and the current date. The header record is written as the first record on the new classification file.

CLASFYG then evaluates the test field using the following steps:

A line of pixel data is read and the greenness value calculated TRJXM for every pixel on the line is called for each of the pixels.

The values for Alpha, Beta, t_0 and the CHI-square are calculated by TRJXM for each pixel.

The line of pixels coefficients for Alpha, Beta and t_0 and the CHI-square value is written to the coefficients file.

Flowchart

Not applicable.

Listing

See Appendix D for program.

3.5.2 SUBROUTINE CROPG

Purpose

CROPG reads and analyzes cards describing the initial guesses for A, alpha, beta and t_0 for the training field, the name of the crop and optionally the sun angle.

Linkages

CROPG is called by CLASFYF.

Interface

Calling sequence:

CALL CROPG (IERROR).

Calling sequence parameters:

<u>Argument</u>	<u>Input/ Output</u>	<u>Description</u>
IERROR	Ø	0 if no error occurs; 1 if error occurs.

Function value:

Not applicable.

Labeled COMMON parameters:

Full description of labeled COMMON blocks are contained in Appendix.

<u>Label</u>	<u>Variable</u>	<u>Element Position</u>	<u>Input/ Output</u>	<u>Description</u>
/USER/	ICROP(4)	1	Ø	Name of crop of interest.
/USER/	ZX(4)	2	Ø	Initial guesses for A, Alpha, Beta and t_0 .

Blank COMMON parameters:

None..

Inputs

<u>Unit</u>	<u>Type</u>	<u>Description</u>
21	Seq. data	User information file (See Section 3.4.1)

Outputs

None.

Storage requirement

Not applicable.

Description

Each record in the user defined parameter file is read and checked to have a valid control word in characters 1 through 4 defining the type of information in characters 11 through 80. If the control word is invalid, an error message is written and the error indicator is set nonzero; otherwise, the information is saved in the appropriate common block element.

Flowchart

Not applicable.

Listing

See Appendix D for program.

3.5.3 FUNCTION MOVSYM

Purpose

MOVSYM moves characters from array CARD to a series of left-justified words in array ITEMP.

Linkages

MOVSYM is called by CROPG.

Interface

Calling sequence:

KOUNT = MOVSYM (CARD, ITEMP).

Calling sequence parameters:

<u>Argument</u>	<u>Input/ Output</u>	<u>Description</u>
CARD	I	80 characters of user supplied data.
ITEMP	Ø	Array of left-justified words.

Function Value:

<u>Name</u>	<u>Description</u>
KOUNT	Count of symbols.

Labeled COMMON parameters:

None.

Blank COMMON parameters:

None.

Inputs

None.

Outputs

None.

Storage Requirement

Not applicable.

Description

MOVSYM separates the characters in array CARD starting at character 11 and creates a series of left-justified words in array ITEMP.

Flowchart

Not applicable.

Listing

See Appendix D for program.

3.5.4 FUNCTION NUMBFL

Purpose

NUMBFL changes floating point numbers from characters in array CARD to computational numbers in array XNMVEC.

Linkages

NUMBFL is called by CROPG.

Interface

Calling sequence:

KOUNT = NUMBFL (CARD, XNMVEC).

Calling sequence parameters:

<u>Argument</u>	<u>Input/ Output</u>	<u>Description</u>
CARD	I	80 characters of user supplied data.
XNMVEC	Ø	Array of floating point computational numbers.

Function value:

<u>Name</u>	<u>Description</u>
KOUNT	Count of floating point numbers.

Labeled COMMON parameters:

None.

Blank COMMON parameters:

None.

Inputs

None.

Outputs

None.

Storage requirement

Not applicable.

Description

NUMBFL separates the characters in array CARD starting at character 11 and creates a series of computational floating point numbers.

Flowchart

Not applicable.

Listing

See Appendix D for program.

3.5.5 RDEXEC

Purpose

RDEXEC reads the segment number, number of acquisitions, acquisition dates and Landsat numbers.

Linkages

RDEXEC is called by CLASFYG.

Interface

Calling sequence:

CALL RDEXEC.

Calling sequence parameters:

None.

Function value:

Not applicable.

Labeled COMMON parameters:

Full description of labeled COMMON blocks are contained in Appendix A.

<u>Label</u>	<u>Variable</u>	<u>Element Position</u>	<u>Input/ Output</u>	<u>Description</u>
/USER/	SUNANG(8)	3	Ø	Sun angle for each acquisition.
/MISC/	NOACQ	1	Ø	Number of acquisitions.
/MISC/	ACQDT(8)	2	Ø	Date for each acquisition.
/MISC/	KSEGM	3	Ø	Segment number.
/MISC/	LANDST(8)	5	Ø	Landsat number for each acquisition.

Blank COMMON parameters:

None.

Inputs

<u>Unit</u>	<u>Type</u>	<u>Description</u>
7	Seq. data	Data from RT&E data base (See Section 3.4.3).

Outputs

None.

Storage requirement

Not applicable.

Description

RDEXEC reads the segment number, number of acquisitions, acquisition dates and Landsat numbers.

Flowchart

Not applicable.

Listing

See Appendix D for listing.

3.5.6 SUBROUTINE RDFLES

Purpose

RDFLES reads 1) the header record and one set of vertices or 2) one line of radiance values.

Linkages

RDFLES is called by CLASFYT.

Interface

Calling sequence:

CALL RDFLES (ITYPE, IDATA, X, Y, IERROR).

Calling sequence numbers:

<u>Argument</u>	<u>Input/ Output</u>	<u>Description</u>
ITYPE	I	1 to read header from each acquisition file and field definition; 2 to read 1 line of radiance values from each acquisition file.
IDATA(856,8)	Ø	Line of radiance values from each acquisition file.
X(4)	IØ	Array of sample vertices defining field.
Y(4)	IØ	Array of line vertices defining field.
IERROR	IØ	0 - no error; 1 - error.

Function value:

Not applicable.

Labeled COMMON parameters:

Full description of labeled COMMON blocks are contained in Appendix A.

<u>Label</u>	<u>Variable</u>	<u>Element Position</u>	<u>Input/ Output</u>	<u>Description</u>
/LINES/	NOACQS	4	I	Number of acquisitions.
/LINES/	NXTLNE	1	IØ	Next line number.

Blank COMMON parameters:

None.

Inputs

<u>Unit</u>	<u>Type</u>	<u>Description</u>
11	Seq. data	Acquisition data for date 1 (See Section 4.3.2).
12	Seq. data	Acquisition data for date 2 (See Section 4.3.2).
13	Seq. data	Acquisition data for date 3 (See Section 4.3.2).
14	Seq. data	Acquisition data for date 4 (See Section 4.3.2).
15	Seq. data	Acquisition data for date 5 (See Section 4.3.2).
16	Seq. data	Acquisition data for date 6 (See Section 4.3.2). Optional.
17	Seq. data	Acquisition data for date 7 (See Section 4.3.2). Optional.
18	Seq. data	Acquisition data for date 8 (See Section 4.3.2). Optional.

Outputs

None.

Storage requirement

Not applicable.

Description

If ITYPE=1, RDFLES reads the header record from each of the universal formatted acquisition data tapes and the vertices for one field. If ITYPE=2, RDFLES reads one line of radiance values for each acquisition.

Flowchart

Not applicable.

Listing

See Appendix D.

3.5.7 SUBROUTINE RDVERT

Purpose

RDVERT reads one set of vertices.

Linkages

RDVERT is called by CLASFYG.

Interface

Calling sequence:

CALL RDVERT (XFLD, YFLD, IERROR).

Calling sequence parameters:

<u>Argument</u>	<u>Input/ Output</u>	<u>Description</u>
XFLD(4)	Ø	Array of sample vertices defining field.
YFLD(4)	Ø	Array of line vertices defining field.
IERROR	Ø	0 - no errors; 1 - error.

Function value:

Not applicable.

Labeled COMMON parameters:

None.

Blank COMMON parameters:

None.

Inputs

<u>Unit</u>	<u>Type</u>	<u>Description</u>
21	Seq. data	User specified data file (See Section 4.3.1).

Outputs

None.

Storage requirement

Not applicable.

Description

RDVERT reads the vertices for one field.

Flowchart

Not applicable.

Listing

See Appendix D.

3.5.8 SUBROUTINE RECT

Purpose

RECT determines if a pixel lies within the specified vertices of a specific area.

Linkages

RECT is called by CLASFYT.

Interface

Calling sequence:

CALL RECT (LINE, PIXEL, YY, XX, ICOR).

Calling sequence parameters:

<u>Argument</u>	<u>Input/ Output</u>	<u>Description</u>
LINE	I	Current line number of pixel.
PIXEL	I	Current sample number of pixel.
YY(4)	I	Array of sample vertices defining field.
XX(4)	I	Array of line vertices defining field.
ICOR	Ø	0 if pixel in field; 1 if pixel not in field.

Function value:

Not applicable.

Labeled COMMON parameters:

None.

Blank COMMON parameters:

None.

Inputs

None.

Outputs

None.

Storage requirement

Not applicable.

Description

The pixel is checked to be a boundary pixel and considered in the training field if it is a boundary pixel. If the pixel is within the minimum and maximum limits of the specified area, the angles created between lines drawn between the pixel and boundary pixels are calculated and summed. If the sum of the angles is 360; the pixel is considered to be in the specified field.

Flowchart

Not applicable.

Listing

See Appendix D for program.

3.5.9 SUBROUTINE SDEV

Purpose

SDEV calculates the mean and standard deviation of a vector.

Linkages

SDEV is called by CLASFYT.

Interface

Calling sequence:

CALL SDEV (X, N, XB, S).

Calling sequence parameters:

<u>Argument</u>	<u>Input/ Output</u>	<u>Description</u>
X(N)	I	Array of values.
N	I	Number of values in array X.
XB	Ø	Mean of values in array X.
S	Ø	Standard deviation of values in array X.

Function value:

Not applicable.

Labeled COMMON parameters:

None.

Blank COMMON parameters:

None.

Inputs

None.

Outputs

None.

Storage requirement

Not applicable.

Description

SDEV calculates the mean (XB) and standard deviation (S) of vector X with N points.

Flowchart

Not applicable.

Listing

See Appendix D for program.

3.5.10 SUBROUTINE TRJXM

Purpose

TRJXM makes a least-square fit to a non-linear function to calculate coefficients for the curve.

Linkages

TRJXM is called by CLASFYG.

Interface

Calling sequence:

```
CALL TRJXM (X, Y, SIGMAY, NFILES, NTERMS, MODE, A DELTAA, SIGMAA,  
FLAMDA, YFIT, CHISQR).
```

Calling sequence parameters:

<u>Argument</u>	<u>Input/ Output</u>	<u>Description</u>
X	I	Array of Julian day/100 for acquisitions.
Y	I	Array of dependent variables.
SIGMAY	I	Array of errors on Y.
NFILES	I	Number of acquisitions.
NTERMS	I	Number of degrees of freedom.
MODE	I	Not used, was switch for calculation weight.
ESTIM	I,0	Array of coefficients A, Alpha, Beta and t_0 .
DELTAA	I	Array of increments for A.
SIGMAA	0	Standard deviations.
FLAMDA	0	Proportion of gradient search.
YFIT	0	Array of fitted values.
CHISQR	0	Residual CHI square value.

<u>Argument</u>	<u>Input/ Output</u>	<u>Description</u>
IND	N/A	Not used.
WEIGHT	I	Array of weighting constants.
IPRINT	I	Print flag to use in debug.

Function value:

Not applicable.

Labeled COMMON parameters:

None.

Blank COMMON parameters:

None.

Inputs

None.

Outputs

None.

Storage requirement

Not applicable.

Description

TRJXM calculates alpha and beta matrices, using the least-square method, for defining all parameters of the curve for the selected pixels in the training field.

The CHI-square value of the starting point is evaluated and the modified curvature matrix is inverted to find the new parameters.

The convergence depends on the CHI-square value and on the size of step.

If the CHI-square value increases, FLAMDA is increased and the process is re-initiated. If the CHI-square value decreases, the process is re-initiated until convergence is obtained. The parameters and uncertainties are evaluated.

Flowchart

Not applicable.

Listing

See Appendix D for program.

3.5.11 SUBROUTINE F2ERVG

Purpose

F2ERVG computes the derivatives of the function of each of the X values.

Linkages

F2ERVG is called by TRJXM.

Interface

Calling sequence:

CALL F2ERVG (X, I, ESTIM, DELTAA, NTERMS, DERIV).

Calling sequence parameters:

<u>Argument</u>	<u>Input/ Output</u>	<u>Description</u>
X	I	Array of time points for acquisition.
I	I	Current index in calling program.
ESTIM	I $\emptyset$	Array of coefficients A, Alpha, Beta and t_0 .
DELTAA	I	Array of increments for A.
NTERMS	I	Number of degrees of freedom.
DERIV	$\emptyset$	Array of derivatives with respect to parameters ESTIM.

Function value:

Not applicable.

Labeled COMMON parameters:

None.

Blank COMMON parameters:

None.

Inputs

None.

Outputs

None.

Storage requirement

Not applicable.

Description

The radiance value and t_0 are set positive. Y is calculated as the radiance value/ t_0 . If Y is less than or equal to 1, the 4 derivatives are set to very small numbers; otherwise, the derivatives are set to calculated values.

Flowchart

Not applicable.

Listing

See Appendix D for program.

3.5.12 FUNCTION FCHISQ

Purpose

FCHISQ calculates the CHI-square value per degree of freedom.

Linkages

FCHISQ is called by TRJFIT and CHNFIT.

Interface

Calling sequence:

GOODFT=FCHISQ (Y, SIGMAY, NPTS, NFREE, MODE, YFIT, WEIGHT).

Calling sequence parameters:

<u>Argument</u>	<u>Input/ Output</u>	<u>Description</u>
Y(NFILES)	I	Array of dependent variables.
SIGMAY(NFILES)	I	Array of errors on Y.
NPTS	I	Number of acquisitions.
NFREE	I	Number of degrees of freedom.
MODE	I	Not used.
YFIT(NFILES)	I	Array of fitted values.
WEIGHT(NFILES)	I	Array of weighting factors.

Function value:

<u>Name</u>	<u>Description</u>
GOODFT	CHI-square value per degree of freedom.

Labeled COMMON parameters:

None.

Blank COMMON parameters:

None.

Inputs

None.

Outputs

None.

Storage requirement

Not applicable.

Description

FCHISQ calculates CHI-square value = $\sum (YFIT-Y)/SIGMA)^2$

Flowchart

Not applicable.

Listing

See Appendix D for program.

3.5.13 FUNCTION F2NCTG

Purpose

F2NCTG calculates the value of DERIV from the radiance value, alpha and beta.

Linkages

F2ERVG is called by TRJXM.

Interface

Calling sequence:

CALL F2NCTG (X, I, ESTIM, IND).

Calling sequence parameters:

<u>Argument</u>	<u>Input/ Output</u>	<u>Description</u>
X(8)	I	Time array of Julian date/100 for each acquisition.
I	I	Index in calling program.
ESTIM(4)	I	Array of coefficients A, Alpha, Beta and t_0 .
IND	N/A	Not used.
DELTA(8)	I	Array incremental values.
NTERMS	I	Number of degrees of freedom.
DERIV(4)	$\emptyset$	Derivatives.

Function value:

<u>Name</u>	<u>Description</u>
YFIT(8)	Array of fitted values.

Labeled COMMON parameters:

None.

Blank COMMON parameters:

None.

Inputs

None.

Outputs

None.

Storage requirement

Not applicable.

Description

F2NCTG calculates the value of the points on the curve from the values of alpha and beta and the current radiance value.

Flowchart

Not applicable.

Listing

See Appendix D for program.

3.5.14 SUBROUTINE MTINV1

Purpose

MTINV1 inverts a matrix of order NORDER.

Linkages

MTINV1 is called by TRJXM.

Interface

Calling sequence:

CALL MTINV1 (ARRAY, NORDER, DET).

Calling sequence parameters:

<u>Argument</u>	<u>Input/ Output</u>	<u>Description</u>
ARRAY(NORDER)	IØ	Matrix.
NORDER	I	Order of matrix.
DET	Ø	Determinate of matrix.

Function value:

None.

Labeled COMMON parameters:

None.

Blank COMMON parameters:

None.

Inputs

None.

Outputs

None.

Storage requirement

Not applicable.

Description

MTINV1 uses the Gauss-Jordan reduction techniques.

Flowchart

Not applicable.

Listing

See Appendix D for program.

3.5.15 FUNCTION NUMBR

Purpose

NUMBR changes integers from character array CARD to computational numbers in array NUMVEC.

Linkages

NUMBR is called by CROPTM.

Interface

Calling sequence:

KOUNT = NUMBR (CARD, NUMVEC).

Calling sequence parameters:

<u>Argument</u>	<u>Input/ Output</u>	<u>Description</u>
CARD	I	80 characters of user supplied data in character format.
NUMVEC	Ø	Array of integer computational numbers.

Function value:

<u>Name</u>	<u>Description</u>
KOUNT	Number of computational integers

Labeled COMMON parameters:

None.

Blank COMMON parameters:

None.

Inputs

None.

Outputs

None.

Storage requirement

Not applicable.

Description

NUMBER separates the characters in array card starting at the 11th character and creates a series of computational integers.

Flowchart

Not applicable.

Listing

See Appendix D for program.

4.0 OPERATION

4.1 OPERATING DESCRIPTION

CLASFYG is operational on the IBM 3031 computer at LARS, West Lafayette, Indiana.

The CLASFYG program is one of the programs of the BADHWAR SYSTEM.

CLASFYG requires the use of a D disk which is assigned as a temporary disk and an E disk which is used to load LARS routines onto. The user therefore, must not assign a disk to his machine using either MODE E or MODE D. These disks will be assigned as needed.

Prior to executing the CLASFYG program the user must establish on his A disk a USER INFORMATION file as described in Section 3.4.1.

4.2 COMMANDS DESCRIPTION

To execute CLASFYG the user will enter the following series of commands which invoke the JOB CONTROL SOFTWARE. These commands are divided into two classes namely (1) FUNCTION commands and (2) PROGRAM commands. The FUNCTION commands, which perform all the functions except executing the program, are reusable, i.e., once they are invoked they remain in effect until reentered. The PROGRAM commands, which simply execute the program, must be reentered each time the program is to be executed.

The following list gives the commands required to execute the CLASFYG program. They are all FUNCTION commands except the PROGRAM command CLASFYG. These commands are to be given in the listed order.

START

CLASFYG.....

END

The following sections describe each of the commands in detail. Input fields are separated by blanks. If more than one word is required to describe an input field, the description is enclosed in pointed brackets <>. If an input is optional the field is enclosed in square brackets []. Do not include these explanatory characters <> [] when actually submitting input to the computer. To enter a command the user types one input per defined input field and separates each field with a blank.

4.2.1 START

The START command spools the user's console file. The use of this command along with the END command will provide a listing of all information appearing on the user console file. (If running an interactive job this is the terminal.) If running a batch job this is a system defined device. The START command is invoked by the user typing the following:

START

4.2.2 CLASFYG

The CLASFYG command is a PROGRAM command is used to invoke the CLASFYG program. All landsat input data is from the LARS RT&E Data Base and a series of programs is required to perform the necessary interface. The following illustrates this software flow.

```
..RTEER (LARS ROUTINE)
CLASFYG.....LCGINF.....SEGALL (LARS ROUTINE)
..TSRTHS....IVALUE
```

For a detailed description of the above JOB CONTROL SOFTWARE see appendix C.

The CLASFYG command must not be given unless the user has established a user's file on his A disk under the file description <SEGMENT NUMBER> USERG as described in Section 3.4.1. Furthermore, the SEGMENT NUMBER must contain all 4 digits of the segment. For example: segment 0882 dictates that the USER INFORMATION file be named:

0882 USERG A

The CLASFYG command is invoked by the user typing the following.

```
CLASFYG <SEGMENT> <ACQ.#1> <ACQ.#2> <ACQ.#3> <ACQ.#4> <ACQ.#5>...<ACQ.#8>
```

As described in Section 3.4.2, the CLASFYG program requires the user to specify a minimum of 5 segment acquisitions as input and a maximum of 8 may be specified.

The classification file output from an execution of CLASFYG is written to a file named <SEGMENT NUMBER> COEF A. The program inputs acquired from the LARS Data Base and the USER INFORMATION file is spooled to the HOUSTON printer.

4.2.3 END

This command closes the user's console file and causes a spooled copy to be sent to the HOUSTON printer. This command has no effect if the START command was not previously issued. The END command is invoked by the user typing the following:

END

4.3 OPERATING EXAMPLE

For our example we assume that the user has established on his A disk the required USER INFORMATION file. In addition since our example deals with an execution using segment 882 the USER INFORMATION file must be established under the filename 0882 and filetype USERG.

COMMAND	EXPLANATION OR ACTION TAKEN
START	Spools the console file.
CLASFYG 0882 78150 78159 78186 78313 78221 78231 78267	Executes the CLASFYG using 7 acquisitions of segment 882.
END	Closes the user's console file and spools the file to the HOUSTON printer.

APPENDIX A

COMMON BLOCK /LINES/

NXTLNE	Not currently used.
LINENO	Current line number.
IDATA(856,8)	Acquisition data.
NOACQS	Number of acquisitions.

COMMON BLOCK /MISC/

NOACQ	Number of acquisitions.
ACQDT(8)	Acquisition dates stored left justified in double precision word.
KSEGM	Segment number stored as 4 character word.
LANDST(8)	Landsat numbers.

COMMON BLOCK /USER/

ICROP(4) Name of crop of interest.
ZX(4,10) Initial guesses for A, Alpha, Beta and t_0 for greenness.
SANGGG(8) Sun angles for acquisitions.

APPENDIX B

CLASFYG Variable Definitions

Variable	Definition
ABS	ABSOLUTE VALUE FUNCTION
ACQDT	ACQUISITION DATES IN ALPHANUMERIC CHARACTER
ACQDTB	ACQUISITION DATES IN 1 CHARACTER WORDS
ALPHBF	BUFFER FOR ALPHA VALUES
ANG	TEMP VALUE, USED IN SUN ANGLE CORRECTION
BETABF	BUFFER FOR BETA VALUES AFTER TEST PIXEL CALL TO TRJXM
BSEG	SEGMENT NUMBER IN CHARACTERS
CHIBUF	BUFFER FOR CH SQ. VALUES
CHISO	FP CHI SQ. VALUE CALC. BY TRJXM FOR CURRENT TEST PIXEL
CHNVAL	HOLD AREA FOR CHANNEL RADIANCE VALUES
CLNDST	CONSTANT FOR CONVERTING LANDSAT 3 DATA
OPTIME	SUBROUTINE TO RETURN TODAY'S DATE AND TIME
DBUF	NOT USED
HDR	BUFFER FOR HEADER
IALPHA	2ND APPRX VALUE, ALPHA, CALC BY TRJXM FOR TEST PIXEL
IBETA	3RD APPRX VALUE, BETA, CALC BY TRJXM FOR CURRENT TEST PIXEL
ICHISO	INTGR CHI SQ. VALUE CALC. FOR CURRENT TEST PIXEL BY TRJXM
ICOR	RETURN PARAMETER FROM RECT, 0=PIXEL IN FLD, 1=PIXEL NOT IN FLD
ICPTIM	INITIAL CP TIME IN HUNDREDTHS OF SECONDS
ICROP	CROP IN ALPHANUMERIC CHARACTERS
ICUT	NOT USED
IDATA	BUFFER AREA FOR LINES OF RADIANCE VALUES
IDATE	ACQUISITION DATES IN INTEGER FORMAT
IDAY	DAY IN CHARACTER FORMAT
IDIFFC	ELAPSED CP TIME IN HUNDREDTHS OF SECONDS
IDIFFV	ELAPSED VIRTUAL CP TIME IN HUNDREDTHS OF SECONDS
IDUPDT	INDEX TO DUPLICATE DATE, ZERO IF NO DUPLICATES
IHOLD1	ARRAY OF 1 CHARACTER WORDS
IHOLD4	ARRAY OF 4 CHARACTER WORDS
II	INDEX
ILIM	SET, BUT NOT USED
IMON	MONTH IN CHARACTER FORMAT
INCR	TEMP VALUE USED IN UNPACKING PIXELS
INDEX	INDEX TO LANDSAT CORRECTION FACTOR
IPIXEL	CURRENT PIXEL
ITO	4TH APPRX VALUE, TO, CALC FOR CURRENT TEST PIXEL BY TRJXM
ITYPE	INPUT TO SUBR. RDFLE TO READ HEADER(1) OR RADIANCE VALUES(2)
IVCPTM	INITIAL VIRTUAL CP TIME
IYEAR	2 CHARACTER YEAR

VARIABLE DEFINITION

ORIGINAL PAGE IS
OF POOR QUALITY

JM	INDEX
JSEGM	SEGMENT NUMBER AS 1 CHARACTER WORDS
KBB	INDEX
KBLANK	CONSTANT OF BLANK
KEQUAL	CONSTANT OF EQUAL MARK
KORNER	INDEX TO VERTICES FOR TEST FIELD
KSEGM	SEGMENT NUMBER AS 4 CHARACTER WORDS
KURACO	CURRENT ACQUISITION
KURCHN	CURRENT CHANNEL
KURPXL	CURRENT PIXEL
LA	INDEX
LANDST	ARRAY OF LANDSAT NUMBERS FOR ACQUISITIONS
LIMIT	MAX CALLS TO TRJXM FOR EACH PIXEL
LINENO	CURRENT LINE NUMBER
LMAX	MAXIMUM LINE NUMBER FOR BOTH FIELDS
LMIN	MINIMUM LINE NUMBER FOR BOTH FIELDS
LOC	TEMP VALUE USED IN UNPACKING RADIANCE VALUES
MAXPXL	MAXIMUM PIXEL
MINPXL	MINIMUM PIXEL
MODE	NOT USED, ORIGINALLY USED TO SELECT WEIGHTING METHOD
NOPTIM	ENDING CP TIME IN HUNDREDTHS OF SECONDS
NMODE	CONSTANT OF 0, USED IN CALL TO TRJXM
NOACO	NUMBER OF ACQUISITIONS
NOACOS	NUMBER OF ACQUISITIONS
NOACOS	NUMBER OF ACQUISITIONS
NOPXLS	NUMBER OF PIXELS
NOTRPX	CURRENT NUMBER OF PIXELS IN TRAINING FIELD
NTERM	NUMBER OF DEGREES OF FREEDOM (4)
NTIME	CURRENT DATE, NOT USED
NVCPTM	ENDING VIRTUAL CP TIME IN HUNDREDTHS OF SECONDS
NXTLNE	NOT USED
PELTA	8TH PARAMETER TRJXM, CAN BE USED IN NON-ANALYTIC DIFFERENTIATION
DELTA	NOT USED
QFTX	11TH PARAMETER IN CALLING SEQUENCE TO TRJXM
RDFILES	SUBROUTINE TO READ FILE DATA
RECT	SUBROUTINE TO DETERMINE IF PIXEL IN USER DEFINED FIELD
SANG	SUN ANGLE ARRAY
SANGGG	USER INPUT SUN ANGLE
SDEV	SUBROUTINE TO CALCULATE MEAN AND ST. DEV.
SETUPG	SUBROUTINE TO READ USER INPUT DATA
SGMATR	ST. DEV. GREEN TRAIN FLD, INDEXED BY ACQ. NO. USED FOR TEST FLD
SIGMA	ERROR ON PARAMETERS FOR RETURN FROM TRJXM
SIGMAG	ST.DEV. FOR TRAINING FIELD
SIN	SINE FUNCTION
STIME	STARTING TIME OF DAY IN CHARACTERS FOR HEADER

ORIGINAL PAGE IS
OF POOR QUALITY

VARIABLE DEFINITION

TIMECP	ELAPSED CP TIME IN MINUTES
TIMEVR	ELAPSED VIRTUAL CP TIME IN MINUTES
TODAY	TODAY'S DATE
TRAINA	1ST APPRX VALUE CALC IN TRJXM FOR TRAIN FLD, USED IN TEST TRJXM
TRALPH	2ND APPRX VALUE CALC. IN TRJXM FOR TRAIN FLD, USED IN TEST TRJXM
TBETA	3RD APPRX VALUE CALC IN TRJXM FOR TRAIN FLD, USED IN TEST TRJXM
TRJXM	SUBROUTINE TO CALCULATE FIT ON TRAINING FLD AND THEN TEST PIXEL
TRT0	4TH APPRX VALUE CALC IN TRJXM FOR TRAIN FLD, USED IN TEST TRJXM
TZERO	4TH APPRX VALUE, T0, CALC FOR CURRENT TEST PIXEL BY TRJXM
TOBUF	BUFFER FOR T0 ARRAY AFTER TEST PIXEL CALLS TO TRJXM
VERTPX	USER SUPPLIED LINE VERTICES
WEIGHT	$1./\text{SIGMA}^2$, WEIGHT FACTOR USED BY STATISTICAL ROUTINES
XBETA	FP 2ND APPRX VALUE CALC. BY TRJXM FOR CURRENT TEST PIXEL
XCHIN	INITIALLY 200, THEN CURRENT VALUE OF CHI SQ AFTER CALLS TO TRJXM
XDAY	FL. PT. VALUES FOR DAYS OF YEAR / 100.
XDIF	FL. PT. TEMP HOLD AREA
XGREEN	GREENNESS VALUES FOR TRAIN PIXELS
XISOP	CHI SQ. AFTER BOTH CALLS TO TRJXM
XLAMDA	INCR PARAMETER, SET $1.E-03$ 1ST CALL TO TRJXM, MODIFIED BY TRJXM
XLINE	FP USER SUPPLIED LINE NUMBER FOR CALL TO RECT
XMEAN	MEAN OF GREENNESS VALUES FOR TRAINING FIELD
XMNTRN	ARRAY OF MEANS FOR TRAINING FIELD ACQUISITIONS
XPIXEL	FP USER SUPPLIED PIXEL NUMBER FOR CALL TO RECT
XPIXGR	ARRAY OF GREENNESS VALUES FOR PIXELS
XTH	TEMP
XTOL	TOLERANCE FACTOR USED FOR TRJXM FIT CHECK
VERTLN	USER SUPPLIED PIXEL VERTICES
YGREEN	GREENNESS VALUES FOR TRAINING FIELD

APPENDIX C

1980-1981

Awards

Suppliment

ADDITIONAL INFORMATION:

ADDITIONAL: $\leq \text{ACO}$. AND NOT A CO-REFINEMENT. THE PROGRAM WILL ACCEPT A.

FOR SALE

EXCEPTIONS

They have also been called "the
lost generation" and "the generation
that did not exist."

ASSIGNMENT 1

ORIGINAL PAGE IS
OF POOR QUALITY

[illegible]

ORIGINAL PAGE IS
OF POOR QUALITY

PAGE 003

FILE: CLASFC: CFC U LANS / DEPT: UNIVERSITY

PRINT AT LISTIC
SPAWN POINT: 2 CLON
KFVH
REFW

REQUESTED OPTIONS: NOTERM

OPTIONS IN EFFECT: NAME(MAIN) OPTIMIZE(1) LINECOUNT(80) SIZE(MAX) AUTODRM (NONE)
SOURCE EBCDIC NOLIST NODECK OBJECT MAP NFORMAT NOGOSTMT XREF ALC NOANSF NOTERM IBM FLAG(11)

PROGRAM LCGINF

GET INFO FROM LARS/WRITE EXEC FOR CLSFY6

HISTORY

M A TOMPKINS LEMSCO 01/27/81 ORIGINAL CODE

METHOD

READ NUMBER OF ACQS... SEGMENT NUMBER AND ACO NUMBERS. ACCESS THE
LARS RTLE DATA BASE. IF SUCCESSFUL WRITE LIST INFO EXEC TO MOUNT
TAPES AND TRANSFER DATA TO DISK FILES. FILEDEF ALL NEW DISK FILES.
WRITE INPUT FILE CONSISTING OF NUMBER OF ACO. SATELITE NUMBER
AND SUN ANGLES FOR EACH ACQUISITION. WRITE SEGMENT NUMBER AND
ACQUISITION NUMBERS FOR DOCUMENTARY PURPOSES.

MACHINE DEPENDENT CODE

NONE.

EXTERNAL REFERENCES

SECALL LARS ROUTINE TO ACQUIRE INFO FROM RTLE DATA BASE
TAGSORT USING HIRSHARD'S SHELL SORT
RTLEERR LARS ERROR ROUTINE

EXCEPTIONS

IF IERR <> 0 OR 4 WRITE ERROR MESSAGE AND WRITE EXEC
TO TERMINATE PROGRAM.

LOCAL DECLARATIONS

ISN 0002	INTEGER INDEX(89,112)	INFO ON EACH ACO REQUESTED FORM DATA BASE
ISN 0003	INTEGER LSEGNO	LANDSAT SEGMENT NUMBER
ISN 0004	INTEGER NACORO	NUMBER OF ACQUISITION REQUESTED
ISN 0005	INTEGER LSEGTP(64)	TEMP FOR TESTING OF LSEGNO
ISN 0006	INTEGER NUMACO	NO. OF ACO REQUESTED: NO. OF ACO. FOUND.
ISN 0007	INTEGER LSEGAD(64)	LANDSAT SEG. ACO. DATE
ISN 0008	INTEGER IERR	RTLE DATA BASE ERROR CODE
ISN 0009	INTEGER LACORQ(5,10)	LANDSAT INFO REQUESTED BY USER
ISN 0010	INTEGER NACORO	NUMBER OF ACO. REQUESTED
ISN 0011	INTEGER INTAG(10)	ORDER TAGS (INDEX)
ISN 0012	INTEGER LSTAPE	LAST TAPE NUMBER
ISN 0013	INTEGER NPLSKP	NUMBER OF FILES TO SKIP
ISN 0014	INTEGER IUNIT	UNIT NUMBER FOR FILE DEFINITION

LCG00010
LCG00020
LCG00030
LCG00040
LCG00050
LCG00060
LCG00070
LCG00080
LCG00090
LCG00100
LCG00110
LCG00120
LCG00130
LCG00140
LCG00150
LCG00160
LCG00170
LCG00180
LCG00190
LCG00200
LCG00210
LCG00220
LCG00230
LCG00240
LCG00250
LCG00260
LCG00270
LCG00280
LCG00290
LCG00300
LCG00310
LCG00320
LCG00330
LCG00340
LCG00350
LCG00360
LCG00370
LCG00380
LCG00390
LCG00400
LCG00410
LCG00420
LCG00430
LCG00440
LCG00450
LCG00460
LCG00470
LCG00480
LCG00490
LCG00500
LCG00510
LCG00520
LCG00530
LCG00540
LCG00550
LCG00560
LCG00570
LCG00580
LCG00590
LCG00600
LCG00610
LCG00620
LCG00630
LCG00640
LCG00650
LCG00660
LCG00670
LCG00680
LCG00690
LCG00700
LCG00710
LCG00720
LCG00730

ORIGINAL PAGE IS
OF POOR QUALITY

PAGE 2

DATE 81.141/13.54.09

05/360 FORTRAN H EXTENDED

MAIN

LEVEL 2-3.0 (JUNE 78)

```

C PROCEDURE
C -----
C
C READ FROM STACK THE NUMBER OF ACO NEEDED, SEGMENT NUMBER, AND
C SPECIFIC ACQUISITIONS SOUGHT.
C
C START WRITING LSTINFO EXEC.
C
C 90 WRITE(2,90)
C 90 FORMAT(1,1,CONTROL OFF)
C
C 100 READ(3,100)NUMACO
C 100 FORMAT(1)
C
C 110 READ(3,110)LSEGNO
C 110 FORMAT(1)
C
C DO 105 I = 1,NUMACO
C 105 READ(3,120)LSEGAQ(I)
C 105 CONTINUE
C
C 120 FORMAT(15)
C
C WHEN CALLING LARS SEGALL ROUTINE THE ARRAY OF ACO MUST NOT
C CONTAIN ANY DUPLICATE ACO NUMBERS. THE LSEGTP ARRAY CONSIST
C OF UNIQUE ACO NUMBERS. NACORO IS THE COUNT OF UNIQUE NUMBERS.
C
C NACORO = 0
C DO 140 K = 1,NUMACO
C 130 J = 1,NUMACO
C IF (LSEGAQ(K).EQ.LSEGTP(J)) GO TO 140
C 130 CONTINUE
C NACORO = NACORO + 1
C LSEGTP(NACORO) = LSEGAQ(K)
C 140 CONTINUE
C
C CALL LARS SEGALL ROUTINE FOR ALL INFO ON THE REQUESTED ACO.
C BECAUSE OF THE POSSIBILITY OF DUPLICATE INFO ON SOME SEGMENTS
C AND THE POSSIBILITY THAT THE ORDER OF THE INFO RETURNED MAY BE
C DIFFERENT FROM REQUESTED SEG ORDER A SEARCH IS REQUIRED TO ORDER
C AND DELETE IF ANY DUPLICATE INFO.
C
C CALL SEGALL(LSEGNO,NACORO,LSEGTP,INDEX,IERR,4,'E')
C
C CHECK IERR MESSAGE IF <> 0 OR 4 CALL LARS RTEERR ROUTINE FOR
C ERROR MESSAGE.
C
C IF (IERR.EQ.0 OR IERR.EQ.4) GO TO 300
C CALL RTEERR(IERR,5)
C WRITE(2,250)
C 250 FORMAT(1,1,STACK 1,/,,' &EXIT')
C GO TO 900
C
C 300 WRITE(2,310)
C 310 FORMAT(1,1,STACK 0)
C
C SEARCH INFO RETURNED FROM DATA BASE. STORE INFO INTO LACORO
C ARRAY.
C
C DO 450 J = 1,NUMACO
C 370 I = 1,NACORO
C IF (INDEX(12,I).EQ.LSFGAQ(I)) GO TO 400
C CONTINUE
C LACORO(1,J) = INDEX(1,1,ITEM)
C LACORO(2,J) = INDEX(2,1,ITEM)
C LACORO(3,J) = INDEX(3,1,ITEM)
C LACORO(4,J) = INDEX(4,1,ITEM)
C LACORO(5,J) = INDEX(5,1,ITEM)
C LACORO(1000,J) = INDEX(1000,1,ITEM)
C 450 CONTINUE
C

```

```

ISN 0015
ISN 0016
ISN 0017
ISN 0018
ISN 0019
ISN 0020
ISN 0021
ISN 0022
ISN 0023
ISN 0024

ISN 0025
ISN 0026
ISN 0027
ISN 0028
ISN 0029
ISN 0030
ISN 0031
ISN 0032
ISN 0033

ISN 0034

ISN 0035
ISN 0036
ISN 0037
ISN 0038
ISN 0039
ISN 0040

ISN 0041
ISN 0042

ISN 0043
ISN 0044
ISN 0045
ISN 0046
ISN 0047
ISN 0048
ISN 0049
ISN 0050
ISN 0051
ISN 0052
ISN 0053
ISN 0054

```


LEVEL 2.3.0 (JUNE 78)

[illegible][illegible][illegible]

*****F O R T R A N C R O S S R E F E R E N C E L I S T I N G *****

LABEL	DEFINED	REFERENCES	00000000
90	0015	0015	0000
005	0016	0016	0000
20	0020	0020	0000
30	0030	0030	0000
40	0030	0030	0000
50	0040	0040	0000
60	0040	0040	0000
70	0040	0040	0000
80	0050	0050	0000
90	0050	0050	0000
000	0050	0050	0000
001	0050	0050	0000
002	0050	0050	0000
003	0050	0050	0000
004	0050	0050	0000
005	0050	0050	0000
006	0050	0050	0000
007	0050	0050	0000
008	0050	0050	0000
009	0050	0050	0000
010	0050	0050	0000
011	0050	0050	0000
012	0050	0050	0000
013	0050	0050	0000
014	0050	0050	0000
015	0050	0050	0000
016	0050	0050	0000
017	0050	0050	0000
018	0050	0050	0000
019	0050	0050	0000
020	0050	0050	0000
021	0050	0050	0000
022	0050	0050	0000
023	0050	0050	0000
024	0050	0050	0000
025	0050	0050	0000
026	0050	0050	0000
027	0050	0050	0000
028	0050	0050	0000
029	0050	0050	0000
030	0050	0050	0000
031	0050	0050	0000
032	0050	0050	0000
033	0050	0050	0000
034	0050	0050	0000
035	0050	0050	0000
036	0050	0050	0000
037	0050	0050	0000
038	0050	0050	0000
039	0050	0050	0000
040	0050	0050	0000
041	0050	0050	0000
042	0050	0050	0000
043	0050	0050	0000
044	0050	0050	0000
045	0050	0050	0000
046	0050	0050	0000
047	0050	0050	0000
048	0050	0050	0000
049	0050	0050	0000
050	0050	0050	0000
051	0050	0050	0000
052	0050	0050	0000
053	0050	0050	0000
054	0050	0050	0000
055	0050	0050	0000
056	0050	0050	0000
057	0050	0050	0000
058	0050	0050	0000
059	0050	0050	0000
060	0050	0050	0000
061	0050	0050	0000
062	0050	0050	0000
063	0050	0050	0000
064	0050	0050	0000
065	0050	0050	0000
066	0050	0050	0000
067	0050	0050	0000
068	0050	0050	0000
069	0050	0050	0000
070	0050	0050	0000
071	0050	0050	0000
072	0050	0050	0000
073	0050	0050	0000
074	0050	0050	0000
075	0050	0050	0000
076	0050	0050	0000
077	0050	0050	0000

NAME		TAG		TYPE		ADD.		NAME		TAG		TYPE		ADD.	
/ MAIN / SIZE OF PROGRAM 009A54 HEXADECIMAL BYTES															

*LEVEL 2.3.0 (JUNE 78)

MAIN

05/360

FORTRAN H EXTENDED

DATE RI.141/13.54.09

PAGE

5

IER SFA
UNIT SFA
LSEGO SFA
NFLSKP SF
TSRINS SF

ITEM SF
IBCOMW SFA
LSEGT SFA
NUMACO SFA

INDEX SFA
LACORO SFA
LSTAPE SFA
RYEERR SF

INTAG SFA
LSEGO SFA
NICORO SFA
SEGALL SFA

000344
000354
000364
000374
000384
000394
000404

SOURCE STATEMENT LABELS

LABEL ISN ADDR
105 23 0092FA
370 4A 0094F0
600 80 009624

COMPILER GENERATED LABELS

LABEL ISN ADDR
100000 1N 009280
100004 2A 00931A
100007 37 009364
100012 5A 00949E
100016 69 009554
100020 81 009630

FORMAT STATEMENT LABELS

LABEL ISN ADDR
90 16 00028A
250 39 000645
530 67 000099
580 77 000171
640 91 0001E0
800 100 000204

LABEL ISN ADDR
100 33 009334
140 54 00947C
900 107 009824

LABEL ISN ADDR
100002 34 009306
100006 37 009334
100009 45 009304
100013 72 009512
100017 86 009686

LABEL ISN ADDR
100 18 000319
310 42 000358
540 70 000499
610 84 00017E
650 93 0001E4
810 102 00021A

*OPTIONS IN EFFECT*NAME(MAIN) OPTIMIZE(1) LINECOUNT(80) SIZE(MAX) AUTOOBL(NONE)

*OPTIONS IN EFFECT*SOURCE EBCDIC NOLIST NODECK OBJECT MAP NOFORMAT NOGOSTMT XREF ALC NOANSF NOTERM IBM FLAG(1)

STATISTICS SOURCE STATEMENTS = 107, PROGRAM SIZE = 38996, SURPROGRAM NAME = MAIN

STATISTICS NO DIAGNOSTICS GENERATED

***** END OF COMPILATION *****

276K BYTES OF CORE NOT USED

ORIGINAL PAGE IS
OF POOR QUALITY

APPENDIX D

[illegible]0029
0026
0028

***OF OR THAN CROSS REFERENCE LISTING,0000

00200
00262
00289

0078
0221
0275

7891

177A

500

002
019
024

0065
0142
0269

0063
0174
0267

162
174
267

1995

185

020
017
009

0051
0161
0269

0951
1560
0163
0265

050
051
064

06
05
04

15	000
16	000
17	000

026
016
005

004
015
026

0046
00A9
02K7

111

LIST I N 00000

[illegible]

SYMBOL	INTERPOL	STAFF	OFFICE	DATE	NAME	CITY	STATE	REFERENCE	LIST	NUMBER
KURACH	0112	0117	0130	0144	0165					
KURACH	0113	0118	0140	0141	0165					
KURACH	0114	0119	0141	0141	0165					
KURACH	0115	0120	0141	0141	0165					
KURACH	0116	0121	0141	0141	0165					
KURACH	0117	0122	0141	0141	0165					
KURACH	0118	0123	0141	0141	0165					
KURACH	0119	0124	0141	0141	0165					
KURACH	0120	0125	0141	0141	0165					
KURACH	0121	0126	0141	0141	0165					
KURACH	0122	0127	0141	0141	0165					
KURACH	0123	0128	0141	0141	0165					
KURACH	0124	0129	0141	0141	0165					
KURACH	0125	0130	0141	0141	0165					
KURACH	0126	0131	0141	0141	0165					
KURACH	0127	0132	0141	0141	0165					
KURACH	0128	0133	0141	0141	0165					
KURACH	0129	0134	0141	0141	0165					
KURACH	0130	0135	0141	0141	0165					
KURACH	0131	0136	0141	0141	0165					
KURACH	0132	0137	0141	0141	0165					
KURACH	0133	0138	0141	0141	0165					
KURACH	0134	0139	0141	0141	0165					
KURACH	0135	0140	0141	0141	0165					
KURACH	0136	0141	0141	0141	0165					
KURACH	0137	0142	0141	0141	0165					
KURACH	0138	0143	0141	0141	0165					
KURACH	0139	0144	0141	0141	0165					
KURACH	0140	0145	0141	0141	0165					
KURACH	0141	0146	0141	0141	0165					
KURACH	0142	0147	0141	0141	0165					
KURACH	0143	0148	0141	0141	0165					
KURACH	0144	0149	0141	0141	0165					
KURACH	0145	0150	0141	0141	0165					
KURACH	0146	0151	0141	0141	0165					
KURACH	0147	0152	0141	0141	0165					
KURACH	0148	0153	0141	0141	0165					
KURACH	0149	0154	0141	0141	0165					
KURACH	0150	0155	0141	0141	0165					
KURACH	0151	0156	0141	0141	0165					
KURACH	0152	0157	0141	0141	0165					
KURACH	0153	0158	0141	0141	0165					
KURACH	0154	0159	0141	0141	0165					
KURACH	0155	0160	0141	0141	0165					
KURACH	0156	0161	0141	0141	0165					
KURACH	0157	0162	0141	0141	0165					
KURACH	0158	0163	0141	0141	0165					
KURACH	0159	0164	0141	0141	0165					
KURACH	0160	0165	0141	0141	0165					
KURACH	0161	0166	0141	0141	0165					
KURACH	0162	0167	0141	0141	0165					
KURACH	0163	0168	0141	0141	0165					
KURACH	0164	0169	0141	0141	0165					
KURACH	0165	0170	0141	0141	0165					
KURACH	0166	0171	0141	0141	0165					
KURACH	0167	0172	0141	0141	0165					
KURACH	0168	0173	0141	0141	0165					
KURACH	0169	0174	0141	0141	0165					
KURACH	0170	0175	0141	0141	0165					
KURACH	0171	0176	0141	0141	0165					
KURACH	0172	0177	0141	0141	0165					
KURACH	0173	0178	0141	0141	0165					
KURACH	0174	0179	0141	0141	0165					
KURACH	0175	0180	0141	0141	0165					
KURACH	0176	0181	0141	0141	0165					
KURACH	0177	0182	0141	0141	0165					
KURACH	0178	0183	0141	0141	0165					
KURACH	0179	0184	0141	0141	0165					
KURACH	0180	0185	0141	0141	0165					
KURACH	0181	0186	0141	0141	0165					
KURACH	0182	0187	0141	0141	0165					
KURACH	0183	0188	0141	0141	0165					
KURACH	0184	0189	0141	0141	0165					
KURACH	0185	0190	0141	0141	0165					
KURACH	0186	0191	0141	0141	0165					
KURACH	0187	0192	0141	0141	0165					
KURACH	0188	0193	0141	0141	0165					
KURACH	0189	0194	0141	0141	0165					
KURACH	0190	0195	0141	0141	0165					
KURACH	0191	0196	0141	0141	0165					
KURACH	0192	0197	0141	0141	0165					
KURACH	0193	0198	0141	0141	0165					
KURACH	0194	0199	0141	0141	0165					
KURACH	0195	0200	0141	0141	0165					
KURACH	0196	0201	0141	0141	0165					
KURACH	0197	0202	0141	0141	0165					
KURACH	0198	0203	0141	0141	0165					
KURACH	0199	0204	0141	0141	0165					
KURACH	0200	0205	0141	0141	0165					
KURACH	0201	0206	0141	0141	0165					
KURACH	0202	0207	0141	0141	0165					
KURACH	0203	0208	0141	0141	0165					
KURACH	0204	0209	0141	0141	0165					
KURACH	0205	0210	0141	0141	0165					
KURACH	0206	0211	0141	0141	0165					
KURACH	0207	0212	0141	0141	0165					
KURACH	0208	0213	0141	0141	0165					
KURACH	0209	0214	0141	0141	0165					
KURACH	0210	0215	0141	0141	0165					
KURACH	0211	0216	0141	0141	0165					
KURACH	0212	0217	0141	0141	0165					
KURACH	0213	0218	0141	0141	0165					
KURACH	0214	0219	0141	0141	0165					
KURACH	0215	0220	0141	0141	0165					
KURACH	0216	0221	0141	0141	0165					
KURACH	0217	0222	0141	0141	0165					
KURACH	0218	0223	0141	0141	0165					
KURACH	0219	0224	0141	0141	0165					
KURACH	0220	0225	0141	0141	0165					
KURACH	0221	0226	0141	0141	0165					
KURACH	0222	0227	0141	0141	0165					
KURACH	0223	0228	0141	0141	0165					
KURACH	0224	0229	0141	0141	0165					
KURACH	0225	0230	0141	0141	0165					
KURACH	0226	0231	0141	0141	0165					
KURACH	0227	0232	0141	0141	0165					
KURACH	0228	0233	0141	0141	0165					
KURACH	0229	0234	0141	0141	0165					
KURACH	0230	0235	0141	0141	0165					
KURACH	0231	0236	0141	0141	0165					
KURACH	0232	0237	0141	0141	0165					
KURACH	0233	0238	0141	0141	0165					
KURACH	0234	0239	0141	0141	0165					
KURACH	0235	0240	0141	0141	0165					
KURACH	0236	0241	0141	0141	0165					
KURACH	0237	0242	0141	0141	0165					
KURACH	0238	0243	0141	0141	0165					
KURACH	0239	0244	0141	0141	0165					
KURACH	0240	0245	0141	0141	0165					
KURACH	0241	0246	0141	0141	0165					
KURACH	0242	0247	0141	0141	0165					
KURACH	0243	0248	0141	0141	0165					
KURACH	0244	0249	0141	0141	0165					
KURACH	0245	0250	0141	0141	0165					
KURACH	0246	0251	0141	0141	0165					
KURACH	0247	0252	0141	0141	0165					
KURACH	0248	0253	0141	0141	0165					
KURACH	0249	0254	0141	0141	0165					
KURACH	0250	0255	0141	0141	0165					
KURACH	0251	0256	0141	0141	0165					
KURACH	0252	0257	0141	0141	0165					
KURACH	0253	0258	0141	0141	0165					
KURACH	0254	0259	0141	0141	0165					
KURACH	0255	0260	0141	0141	0165					
KURACH	0256	0261	0141	0141	0165					
KURACH	0257	0262	0141	0141	0165					
KURACH	0258	0263	0141	0141	0165					
KURACH	0259	0264	0141	0141	0165					
KURACH	0260	0265	0141	0141	0165					
KURACH	0261	0266	0141	0141	0165					
KURACH	0262	0267	0141	0141	0165					
KURACH	0263	0268	0141	0141	0165					
KURACH	0264	0269	0141	0141	0165					
KURACH	0265	0270	0141	0141	0165					
KURACH	0266	0271	0141	0141	0165					
KURACH	0267	0272	0141	0141	0165					
KURACH	0268	0273	0141	0141	0165					
KURACH	0269	0274	0141	0141	0165					
KURACH	0270	0275	0141	0141	0165					
KURACH	0271	0276	0141	0141	0165					
KURACH	0272	0277	0141	0141	0165					
KURACH	0273	0278	0141	0141	0165					</

[illegible]

•LEVFL 2.3.0 (JUN 7A)

www.wfnr.com

LAHFL OFF 10:50

LAFI

WATER /

-

NAME	TAG	TYPE	ADDR
NAIVE	SF	104	000004C
M	SF	104	000005C
NR	SF	104	000006C
K	SF	104	000007C
K1	SF	104	000008C
K2	SF	104	000009C
K3	SF	104	00000AC
K4	SF	104	00000BC
K5	SF	104	00000CC
K6	SF	104	00000DC
K7	SF	104	00000EC
K8	SF	104	00000FC
K9	SF	104	000010C
K10	SF	104	000011C
K11	SF	104	000012C
K12	SF	104	000013C
K13	SF	104	000014C
K14	SF	104	000015C
K15	SF	104	000016C
K16	SF	104	000017C
K17	SF	104	000018C
K18	SF	104	000019C
K19	SF	104	00001AC
K20	SF	104	00001BC
K21	SF	104	00001CC
K22	SF	104	00001DC
K23	SF	104	00001EC
K24	SF	104	00001FC
K25	SF	104	000020C
K26	SF	104	000021C
K27	SF	104	000022C
K28	SF	104	000023C
K29	SF	104	000024C
K30	SF	104	000025C
K31	SF	104	000026C
K32	SF	104	000027C
K33	SF	104	000028C
K34	SF	104	000029C
K35	SF	104	00002AC
K36	SF	104	00002BC
K37	SF	104	00002CC
K38	SF	104	00002DC
K39	SF	104	00002EC
K40	SF	104	00002FC
K41	SF	104	000030C
K42	SF	104	000031C
K43	SF	104	000032C
K44	SF	104	000033C
K45	SF	104	000034C
K46	SF	104	000035C
K47	SF	104	000036C
K48	SF	104	000037C
K49	SF	104	000038C
K50	SF	104	000039C
K51	SF	104	00003AC
K52	SF	104	00003BC
K53	SF	104	00003CC
K54	SF	104	00003DC
K55	SF	104	00003EC
K56	SF	104	00003FC
K57	SF	104	000040C
K58	SF	104	000041C
K59	SF	104	000042C
K60	SF	104	000043C
K61	SF	104	000044C
K62	SF	104	000045C
K63	SF	104	000046C
K64	SF	104	000047C
K65	SF	104	000048C
K66	SF	104	000049C
K67	SF	104	00004AC
K68	SF	104	00004BC
K69	SF	104	00004CC
K70	SF	104	00004DC
K71	SF	104	00004EC
K72	SF	104	00004FC
K73	SF	104	000050C
K74	SF	104	000051C
K75	SF	104	000052C
K76	SF	104	000053C
K77	SF	104	000054C
K78	SF	104	000055C
K79	SF	104	000056C
K80	SF	104	000057C
K81	SF	104	000058C
K82	SF	104	000059C
K83	SF	104	00005AC
K84	SF	104	00005BC
K85	SF	104	00005CC
K86	SF	104	00005DC
K87	SF	104	00005EC
K88	SF	104	00005FC
K89	SF	104	000060C
K90	SF	104	000061C
K91	SF	104	000062C
K92	SF	104	000063C
K93	SF	104	000064C
K94	SF	104	000065C
K95	SF	104	000066C
K96	SF	104	000067C
K97	SF	104	000068C
K98	SF	104	000069C
K99	SF	104	00006AC
K100	SF	104	00006BC
K101	SF	104	00006CC
K102	SF	104	00006DC
K103	SF	104	00006EC
K104	SF	104	0000

D-13

LEVEL	2.3.0 (NAME)	MAIN	05/300	FOURTH	W EXTENDED	DATE	11.130/13.16.48	PAGE	14
NAME OF COMMON BLOCK	NAME	LINE	SIZE	OF BLOCK	HEXADECIMAL	BYTES			
	VAR. NAME	REL. ADDR.	VAR. NAME	REL. ADDR.	VAR. NAME	TYPE	REL. ADDR.		
	104	000000	NO	104	000004	104	000004	001AC8	
NAME OF COMMON BLOCK	NAME	LINE	SIZE	OF BLOCK	HEXADECIMAL	BYTES			
	VAR. NAME	REL. ADDR.	VAR. NAME	REL. ADDR.	VAR. NAME	TYPE	REL. ADDR.		
	104	000000	NO	104	000008	104	000044	00004C	NO
EQUIVALENT VARIABLES WITHIN THIS COMMON BLOCK	VAR. NAME	REL. ADDR.	VAR. NAME	REL. ADDR.	VAR. NAME	TYPE	REL. ADDR.		
	104	000000	NO	104	000008	104	000044	00004C	NO
	104	000000	NO	104	000008	104	000044	00004C	NO
EQUIVALENT VARIABLES WITHIN THIS COMMON BLOCK	VAR. NAME	REL. ADDR.	VAR. NAME	REL. ADDR.	VAR. NAME	TYPE	REL. ADDR.		
	104	000000	NO	104	000008	104	000044	00004C	NO
	104	000000	NO	104	000008	104	000044	00004C	NO
NAME OF COMMON BLOCK	NAME	LINE	SIZE	OF BLOCK	HEXADECIMAL	BYTES			
	VAR. NAME	REL. ADDR.	VAR. NAME	REL. ADDR.	VAR. NAME	TYPE	REL. ADDR.		
	104	000000	NO	104	000008	104	000044	00004C	NO

SOURCE STATEMENT 1 ARFIS

[illegible]

COMPLI EP (GIFEPATE) LAHFLS

LABEL	TEN	ADDR
000000	1	000070
000001	60	000071
000002	61	000072
000003	62	000073
000004	63	000074
000005	64	000075
000006	65	000076
000007	66	000077
000008	67	000078
000009	68	000079
000010	69	000080
000011	70	000081
000012	71	000082
000013	72	000083
000014	73	000084
000015	74	000085
000016	75	000086
000017	76	000087
000018	77	000088
000019	78	000089
000020	79	000090
000021	80	000091
000022	81	000092
000023	82	000093
000024	83	000094
000025	84	000095
000026	85	000096
000027	86	000097
000028	87	000098
000029	88	000099
000030	89	000100
000031	90	000101
000032	91	000102
000033	92	000103
000034	93	000104
000035	94	000105
000036	95	000106
000037	96	000107
000038	97	000108
000039	98	000109
000040	99	000110
000041	00	000111
000042	01	000112
000043	02	000113
000044	03	000114
000045	04	000115
000046	05	000116
000047	06	000117
000048	07	000118
000049	08	000119
000050	09	000120
000051	10	000121
000052	11	000122
000053	12	000123
000054	13	000124
000055	14	000125
000056	15	000126
000057	16	000127
000058	17	000128
000059	18	000129
000060	19	000130
000061	20	000131
000062	21	000132
000063	22	000133
000064	23	000134
000065	24	000135
000066	25	000136
000067	26	000137
000068	27	000138
000069	28	000139
000070	29	000140
000071	30	000141
000072	31	000142
000073	32	000143
000074	33	000144
000075	34	000145
000076	35	000146
000077	36	000147
000078	37	000148
000079	38	000149
000080	39	000150
000081	40	000151
000082	41	000152
000083	42	000153
000084	43	000154
000085	44	000155
000086	45	000156
000087	46	000157
000088	47	000158
000089	48	000159
000090	49	000160
000091	50	000161
000092	51	000162
000093	52	000163
000094	53	000164
000095	54	000165
000096	55	000166
000097	56	000167
000098	57	000168
000099	58	000169
000100	59	000170
000101	60	000171
000102	61	000172
000103	62	000173
000104	63	000174
000105	64	000175
000106	65	000176
000107	66	000177
000108	67	000178
000109	68	000179
000110	69	000180
000111	70	000181
000112	71	000182
000113	72	000183
000114	73	000184
000115	74	000185
000116	75	000186
000117	76	000187
000118	77	000188
000119</		

FORMAT STATISTICAL AGENCY

[illegible]

ORIGINAL PAGE IS
OF POOR QUALITY

PAGE 15

DATE 81.139/13.16.48 949 410 000489 HR

05/160 FORTMAN H EXTENDED
R449 409 000480

MAIN
R449 310 000477
6011 426 000480

LEVEL 2.3.0 (LINE 70)
6022 309 000467
6010 414 000444

OPTIONS IN EFFECT: NAME (MAIN) OPTIMIZ(1) LINECOUNT(R0) SIZE(FMAX) AUTO(0) (NONE)
OPTIONS IN EFFECT: SOURCE EPOCHIC HOLIST NODECK OBJECT MAP INFORMATION NOGOSINT XREF ALC NOANSF NOTERM IBM FLAG(1)
STATISTICS* SOURCE STATEMENTS = 421, PROGRAM SIZE = 46204, SUBPROGRAM NAME = MAIN
STATISTICS* NO DIAGNOSTICS GENERATED
***** END OF COMPILATION *****

212K BYTES OF CORE NOT USED

DETERMINED OPTIONS: NONE

OPTIONS IN EFFECT: NAME(4) OPTIMIZE(1) LINECOUNT(0) SIZE INDEX: AUTODIAG (NONE)
CHECK: FUTURE INDEX OBJECT MAP INFORMATION MISSING! AREF AIC HONANSF NOTERM 194 FLAG(1)

```

TSN 0002 C SUBROUTINE CHOPG (IER=0)
TSN 0003 C   LOGIC INTEGER (A-X)
TSN 0004 C   CHOPG: READ AND ANALYZE LINES DESCRIBING THE FOLLOWING---
TSN 0005 C   CROP TO BE EVALUATED (4A)
TSN 0006 C   INITIAL VALUES FOR 4 CHANNELS
TSN 0007 C
TSN 0008 C   COMMON /USER/ ICROP(4),ZX(4),SUNANG(R)
TSN 0009 C   DIMENSION LINE(40), ITEMP(64)
TSN 0010 C   DIMENSION TYPES(5)
TSN 0011 C   DATA TYPES /CROP, 2, 3, 4, 5, 6, 7, 8, 9, 10, 11, 12, 13, 14, 15, 16, 17, 18, 19, 20, 21, 22, 23, 24, 25, 26, 27, 28, 29, 30, 31, 32, 33, 34, 35, 36, 37, 38, 39, 40, 41, 42, 43, 44, 45, 46, 47, 48, 49, 50, 51, 52, 53, 54, 55, 56, 57, 58, 59, 60, 61, 62, 63, 64, 65, 66, 67, 68, 69, 70, 71, 72, 73, 74, 75, 76, 77, 78, 79, 80, 81, 82, 83, 84, 85, 86, 87, 88, 89, 90, 91, 92, 93, 94, 95, 96, 97, 98, 99, 100, 101, 102, 103, 104, 105, 106, 107, 108, 109, 110, 111, 112, 113, 114, 115, 116, 117, 118, 119, 120, 121, 122, 123, 124, 125, 126, 127, 128, 129, 130, 131, 132, 133, 134, 135, 136, 137, 138, 139, 140, 141, 142, 143, 144, 145, 146, 147, 148, 149, 150, 151, 152, 153, 154, 155, 156, 157, 158, 159, 160, 161, 162, 163, 164, 165, 166, 167, 168, 169, 170, 171, 172, 173, 174, 175, 176, 177, 178, 179, 180, 181, 182, 183, 184, 185, 186, 187, 188, 189, 190, 191, 192, 193, 194, 195, 196, 197, 198, 199, 200, 201, 202, 203, 204, 205, 206, 207, 208, 209, 210, 211, 212, 213, 214, 215, 216, 217, 218, 219, 220, 221, 222, 223, 224, 225, 226, 227, 228, 229, 230, 231, 232, 233, 234, 235, 236, 237, 238, 239, 240, 241, 242, 243, 244, 245, 246, 247, 248, 249, 250, 251, 252, 253, 254, 255, 256, 257, 258, 259, 260, 261, 262, 263, 264, 265, 266, 267, 268, 269, 270, 271, 272, 273, 274, 275, 276, 277, 278, 279, 280, 281, 282, 283, 284, 285, 286, 287, 288, 289, 290, 291, 292, 293, 294, 295, 296, 297, 298, 299, 300, 301, 302, 303, 304, 305, 306, 307, 308, 309, 310, 311, 312, 313, 314, 315, 316, 317, 318, 319, 320, 321, 322, 323, 324, 325, 326, 327, 328, 329, 330, 331, 332, 333, 334, 335, 336, 337, 338, 339, 340, 341, 342, 343, 344, 345, 346, 347, 348, 349, 350, 351, 352, 353, 354, 355, 356, 357, 358, 359, 360, 361, 362, 363, 364, 365, 366, 367, 368, 369, 370, 371, 372, 373, 374, 375, 376, 377, 378, 379, 380, 381, 382, 383, 384, 385, 386, 387, 388, 389, 390, 391, 392, 393, 394, 395, 396, 397, 398, 399, 400, 401, 402, 403, 404, 405, 406, 407, 408, 409, 410, 411, 412, 413, 414, 415, 416, 417, 418, 419, 420, 421, 422, 423, 424, 425, 426, 427, 428, 429, 430, 431, 432, 433, 434, 435, 436, 437, 438, 439, 440, 441, 442, 443, 444, 445, 446, 447, 448, 449, 450, 451, 452, 453, 454, 455, 456, 457, 458, 459, 460, 461, 462, 463, 464, 465, 466, 467, 468, 469, 470, 471, 472, 473, 474, 475, 476, 477, 478, 479, 480, 481, 482, 483, 484, 485, 486, 487, 488, 489, 490, 491, 492, 493, 494, 495, 496, 497, 498, 499, 500, 501, 502, 503, 504, 505, 506, 507, 508, 509, 510, 511, 512, 513, 514, 515, 516, 517, 518, 519, 520, 521, 522, 523, 524, 525, 526, 527, 528, 529, 530, 531, 532, 533, 534, 535, 536, 537, 538, 539, 540, 541, 542, 543, 544, 545, 546, 547, 548, 549, 550, 551, 552, 553, 554, 555, 556, 557, 558, 559, 560, 561, 562, 563, 564, 565, 566, 567, 568, 569, 570, 571, 572, 573, 574, 575, 576, 577, 578, 579, 580, 581, 582, 583, 584, 585, 586, 587, 588, 589, 590, 591, 592, 593, 594, 595, 596, 597, 598, 599, 600, 601, 602, 603, 604, 605, 606, 607, 608, 609, 610, 611, 612, 613, 614, 615, 616, 617, 618, 619, 620, 621, 622, 623, 624, 625, 626, 627, 628, 629, 630, 631, 632, 633, 634, 635, 636, 637, 638, 639, 640, 641, 642, 643, 644, 645, 646, 647, 648, 649, 650, 651, 652, 653, 654, 655, 656, 657, 658, 659, 660, 661, 662, 663, 664, 665, 666, 667, 668, 669, 670, 671, 672, 673, 674, 675, 676, 677, 678, 679, 680, 681, 682, 683, 684, 685, 686, 687, 688, 689, 690, 691, 692, 693, 694, 695, 696, 697, 698, 699, 700, 701, 702, 703, 704, 705, 706, 707, 708, 709, 710, 711, 712, 713, 714, 715, 716, 717, 718, 719, 720, 721, 722, 723, 724, 725, 726, 727, 728, 729, 730, 731, 732, 733, 734, 735, 736, 737, 738, 739, 740, 741, 742, 743, 744, 745, 746, 747, 748, 749, 750, 751, 752, 753, 754, 755, 756, 757, 758, 759, 760, 761, 762, 763, 764, 765, 766, 767, 768, 769, 770, 771, 772, 773, 774, 775, 776, 777, 778, 779, 780, 781, 782, 783, 784, 785, 786, 787, 788, 789, 790, 791, 792, 793, 794, 795, 796, 797, 798, 799, 800, 801, 802, 803, 804, 805, 806, 807, 808, 809, 810, 811, 812, 813, 814, 815, 816, 817, 818, 819, 820, 821, 822, 823, 824, 825, 826, 827, 828, 829, 830, 831, 832, 833, 834, 835, 836, 837, 838, 839, 840, 841, 842, 843, 844, 845, 846, 847, 848, 849, 850, 851, 852, 853, 854, 855, 856, 857, 858, 859, 860, 861, 862, 863, 864, 865, 866, 867, 868, 869, 870, 871, 872, 873, 874, 875, 876, 877, 878, 879, 880, 881, 882, 883, 884, 885, 886, 887, 888, 889, 890, 891, 892, 893, 894, 895, 896, 897, 898, 899, 900, 901, 902, 903, 904, 905, 906, 907, 908, 909, 910, 911, 912, 913, 914, 915, 916, 917, 918, 919, 920, 921, 922, 923, 924, 925, 926, 927, 928, 929, 930, 931, 932, 933, 934, 935, 936, 937, 938, 939, 940, 941, 942, 943, 944, 945, 946, 947, 948, 949, 950, 951, 952, 953, 954, 955, 956, 957, 958, 959, 960, 961, 962, 963, 964, 965, 966, 967, 968, 969, 970, 971, 972, 973, 974, 975, 976, 977, 978, 979, 980, 981, 982, 983, 984, 985, 986, 987, 988, 989, 990, 991, 992, 993, 994, 995, 996, 997, 998, 999, 1000, 1001, 1002, 1003, 1004, 1005, 1006, 1007, 1008, 1009, 1010, 1011, 1012, 1013, 1014, 1015, 1016, 1017, 1018, 1019, 1020, 1021, 1022, 1023, 1024, 1025, 1026, 1027, 1028, 1029, 1030, 1031, 1032, 1033, 1034, 1035, 1036, 1037, 1038, 1039, 1040, 1041, 1042, 1043, 1044, 1045, 1046, 1047, 1048, 1049, 1050, 1051, 1052, 1053, 1054, 1055, 1056, 1057, 1058, 1059, 1060, 1061, 1062, 1063, 1064, 1065, 1066, 1067, 1068, 1069, 1070, 1071, 1072, 1073, 1074, 1075, 1076, 1077, 1078, 1079, 1080, 1081, 1082, 1083, 1084, 1085, 1086, 1087, 1088, 1089, 1090, 1091, 1092, 1093, 1094, 1095, 1096, 1097, 1098, 1099, 1100, 1101, 1102, 1103, 1104, 1105, 1106, 1107, 1108, 1109, 1110, 1111, 1112, 1113, 1114, 1115, 1116, 1117, 1118, 1119, 1120, 1121, 1122, 1123, 1124, 1125, 1126, 1127, 1128, 1129, 1130, 1131, 1132, 1133, 1134, 1135, 1136, 1137, 1138, 1139, 1140, 1141, 1142, 1143, 1144, 1145, 1146, 1147, 1148, 1149, 1150, 1151, 1152, 1153, 1154, 1155, 1156, 1157, 1158, 1159, 1160, 1161, 1162, 1163, 1164, 1165, 1166, 1167, 1168, 1169, 1170, 1171, 1172, 1173, 1174, 1175, 1176, 1177, 1178, 1179, 1180, 1181, 1182, 1183, 1184, 1185, 1186, 1187, 1188, 1189, 1190, 1191, 1192, 1193, 1194, 1195, 1196, 1197, 1198, 1199, 1200, 1201, 1202, 1203, 1204, 1205, 1206, 1207, 1208, 1209, 1210, 1211, 1212, 1213, 1214, 1215, 1216, 1217, 1218, 1219, 1220, 1221, 1222, 1223, 1224, 1225, 1226, 1227, 1228, 1229, 1230, 1231, 1232, 1233, 1234, 1235, 1236, 1237, 1238, 1239, 1240, 1241, 1242, 1243, 1244, 1245, 1246, 1247, 1248, 1249, 1250, 1251, 1252, 1253, 1254, 1255, 1256, 1257, 1258, 1259, 1260, 1261, 1262, 1263, 1264, 1265, 1266, 1267, 1268, 1269, 1270, 1271, 1272, 1273, 1274, 1275, 1276, 1277, 1278, 1279, 1280, 1281, 1282, 1283, 1284, 1285, 1286, 1287, 1288, 1289, 1290, 1291, 1292, 1293, 1294, 1295, 1296, 1297, 1298, 1299, 1300, 1301, 1302, 1303, 1304, 1305, 1306, 1307, 1308, 1309, 1310, 1311, 1312, 1313, 1314, 1315, 1316, 1317, 1318, 1319, 1320, 1321, 1322, 1323, 1324, 1325, 1326, 1327, 1328, 1329, 1330, 1331, 1332, 1333, 1334, 1335, 1336, 1337, 1338, 1339, 1340, 1341, 1342, 1343, 1344, 1345, 1346, 1347, 1348, 1349, 1350, 1351, 1352, 1353, 1354, 1355, 1356, 1357, 1358, 1359, 1360, 1361, 1362, 1363, 1364, 1365, 1366, 1367, 1368, 1369, 1370, 1371, 1372, 1373, 1374, 1375, 1376, 1377, 1378, 1379, 1380, 1381, 1382, 1383, 1384, 1385, 1386, 1387, 1388, 1389, 1390, 1391, 1392, 1393, 1394, 1395, 1396, 1397, 1398, 1399, 1400, 1401, 1402, 1403, 1404, 1405, 1406, 1407, 1408, 1409, 1410, 1411, 1412, 1413, 1414, 1415, 1416, 1417, 1418, 1419, 1420, 1421, 1422, 1423, 1424, 1425, 1426, 1427, 1428, 1429, 1430, 1431, 1432, 1433, 1434, 1435, 1436, 1437, 1438, 1439, 1440, 1441, 1442, 1443, 1444, 1445, 1446, 1447, 1448, 1449, 1450, 1451, 1452, 1453, 1454, 1455, 1456, 1457, 1458, 1459, 1460, 1461, 1462, 1463, 1464, 1465, 1466, 1467, 1468, 1469, 1470, 1471, 1472, 1473, 1474, 1475, 1476, 1477, 1478, 1479, 1480, 1481, 1482, 1483, 1484, 1485, 1486, 1487, 1488, 1489, 1490, 1491, 1492, 1493, 1494, 1495, 1496, 1497, 1498, 1499, 1500, 1501, 1502, 1503, 1504, 1505, 1506, 1507, 1508, 1509, 1510, 1511, 1512, 1513, 1514, 1515, 1516, 1517, 1518, 1519, 1520, 1521, 1522, 1523, 1524, 1525, 1526, 1527, 1528, 1529, 1530, 1531, 1532, 1533, 1534, 1535, 1536, 1537, 1538, 1539, 1540, 1541, 1542, 1543, 1544, 1545, 1546, 1547, 1548, 1549, 1550, 1551, 1552, 1553, 1554, 1555, 1556, 1557, 1558, 1559, 1560, 1561, 1562, 1563, 1564, 1565, 1566, 1567, 1568, 1569, 1570, 1571, 1572, 1573, 1574, 1575, 1576, 1577, 1578, 1579, 1580, 1581, 1582, 1583, 1584, 1585, 1586, 1587, 1588, 1589, 1590, 1591, 1592, 1593, 1594, 1595, 1596, 1597, 1598, 1599, 1600, 1601, 1602, 1603, 1604, 1605, 1606, 1607, 1608, 1609, 1610, 1611, 1612, 1613, 1614, 1615, 1616, 1617, 1618, 1619, 1620, 1621, 1622, 1623, 1624, 1625, 1626, 1627, 1628, 1629, 1630, 1631, 1632, 1633, 1634, 1635, 1636, 1637, 1638, 1639, 1640, 1641, 1642, 1643, 1644, 1645, 1646, 1647, 1648, 1649, 1650, 1651, 1652, 1653, 1654, 1655, 1656, 1657, 1658, 1659, 1660, 1661, 1662, 1663, 1664, 1665, 1666, 1667, 1668, 1669, 1670, 1671, 1672, 1673, 1674, 1675, 1676, 1677, 1678, 1679, 1680, 1681, 1682, 1683, 1684, 1685, 1686, 1687, 1688, 1689, 1690, 1691, 1692, 1693, 1694, 1695, 1696, 1697, 1698, 1699, 1700, 1701, 1702, 1703, 1704, 1705, 1706, 1707, 1708, 1709, 1710, 1711, 1712, 1713, 1714, 1715, 1716, 1717, 1718, 1719, 1720, 1721, 1722, 1723, 1724, 1725, 1726, 1727, 1728, 1729, 1730, 1731, 1732, 1733, 1734, 1735, 1736, 1737, 1738, 1739, 1740, 1741, 1742, 1743, 1744, 1745, 1746, 1747, 1748, 1749, 1750, 1751, 1752, 1753, 1754, 1755, 1756, 1757, 1758, 1759, 1760, 1761, 1762, 1763, 1764, 1765, 1766, 1767, 1768, 1769, 1770, 1771, 1772, 1773, 1774, 1775, 1776, 1777, 1778, 1779, 1780, 1781, 1782, 1783, 1784, 1785, 1786, 1787, 1788, 1789, 1790, 1791, 1792, 1793, 1794, 1795, 1796, 1797, 1798, 1799, 1800, 1801, 1802, 1803, 1804, 1805, 1806, 1807, 1808, 1809, 1810, 1811, 1812, 1813, 1814, 1815, 1816, 1817, 1818, 1819, 1820, 1821, 1822, 1823, 1824, 1825, 1826, 1827, 1828, 1829, 1830, 1831, 1832, 1833, 1834, 1835, 1836, 1837, 1838, 1839, 1840, 1841, 1842, 1843, 1844, 1845, 1846, 1847, 1848, 1849, 1850, 1851, 1852, 1853, 1854, 1855, 1856, 1857, 1858, 1859, 1860, 1861, 1862, 1863, 1864, 1865, 1866, 1867, 1868, 1869, 1870, 1871, 1872, 1873, 1874, 1875, 1876, 1877, 1878, 1879, 1880, 1881, 1882, 1883, 1884, 1885, 1886, 1887, 1888, 1889, 1890, 1891, 1892, 1893, 1894, 1895, 1896, 1897, 1898, 1899, 1900, 1901, 1902, 1903, 1904, 1905, 1906, 1907, 1908, 1909, 1910, 1911, 1912, 1913, 1914, 1915, 1916, 1917, 1918, 1919, 1920, 1921, 1922, 1923, 1924, 1925, 1926, 1927, 1928, 1929, 1930, 1931, 1932, 1933, 1934, 1935, 1936, 1937, 1938, 1939, 1940, 1941, 1942, 1943, 1944, 1945, 1946, 1947, 1948, 1949, 1950, 1951, 1952, 1953, 1954, 1955, 1956, 1957, 1958, 1959, 1960, 1961, 1962, 1963, 1964, 1965, 1966, 1967, 1968, 1969, 1970, 1971, 1972, 1973, 1974, 1975, 1976, 1977, 1978, 1979, 1980, 1981, 1982, 1983, 1984, 1985, 1986, 1987, 1988, 1989, 1990, 1991, 1992, 1993, 1994, 1995, 1996, 1997, 1998, 1999, 2000, 2001, 2002, 2003, 2004, 2005, 2006, 2007, 2008, 2009, 2010, 2011, 2012, 2013, 2014, 2015, 2016, 2017, 2018, 2019, 2020, 2021, 2022, 2023, 2024, 2025, 2026, 2027, 2028, 2029, 2030, 2031, 2032, 2033, 2034, 2035, 2036, 2037, 2038, 2039, 2040, 2041, 2042, 2043, 2044, 2045, 2046, 2047, 2048, 2049, 2050, 2051, 2052, 2053, 2054, 2055, 2056, 2057, 2058, 2059, 2060, 2061, 2062, 2063, 2064, 2065, 2066, 2067, 2068, 2069, 2070, 2071, 2072, 2073, 2074, 2075, 2076, 2077, 2078, 2079, 2080, 2081, 2082, 2083, 2084, 2085, 2086, 2087, 2088, 2089, 2090, 2091, 2092, 2093, 2094, 2095, 2096, 2097, 2098, 2099, 2100, 2101, 2102, 2103, 2104, 2105, 2106, 2107, 2108, 2109, 2110, 2111, 2112, 2113, 2114, 2115, 2116, 2117, 2118, 2119, 2120, 2121, 2122, 2123, 2124, 2125, 2126, 2127, 2128, 2129, 2130, 2131, 2132, 2133, 2134, 2135, 2136, 2137, 2138, 2139, 2140, 2141, 2142, 2143, 2144, 2145, 2146, 214
```


D-18

292K BYTES OF COPE NOT USED

ORIGINAL PAGE IS
OF POOR QUALITY

PAGE 1

DATE 81.141/14.02.20

05/360 FORTRAN M EXTENDED

*LEVEL 2.3.0 (JUNE 78)

REQUESTED OPTIONS: NOTERM

OPTIONS IN EFFECT: NAME(MAIN) OPTIMIZE(1) LINECOUNT(80) SIZE(MAX) AUTODBL(NONE)
SOURCE EBCDIC NOLIST NODECK OBJECT MAP NOFORMAT NOGOSYMT XREF ALC NOANSF NOTERM IBM FLAG(1)

```
ISN 0002      C      FUNCTION MOVSYM (CARD, ITEM)  
ISN 0003      C      PURPOSE: DECODE CARD OF FORM SYMBOL1, SYMBOL2, ... SYMBOLN  
ISN 0004      C      REAL*8 ITEM(30), ITHOLD8  
ISN 0005      C      LOGICAL*1 ICHAR(1), ITHOLD(8), IBLNK1  
ISN 0006      C      INTEGER*4 CARD(1)  
ISN 0007      C      EQUIVALENCE (ICARD(1), ICHAR(1), ITHOLD(1), ITHOLD8)  
ISN 0008      C      DATA IBLNK1, ICHAR(1), ITHOLD(1), ITHOLD8  
ISN 0009      C      DO 2 I = 1, 8  
ISN 0010      C      ITHOLD(I) = IBLNK1  
ISN 0011      C      NDEX = 0  
ISN 0012      C      DO 100 KOL = 1, 80  
ISN 0013      C      ICHAR(KOL) = CARD(KOL)  
ISN 0014      C      IF (ICARD(1).NE. IBLNK1) GO TO 10  
ISN 0015      C      BLANK  
ISN 0016      C      IF (KOL.FO. 80 .AND. NDEX.NE. 0) GO TO 80  
ISN 0017      C      GO TO 100  
ISN 0018      C      NOT BLANK  
ISN 0019      C      IF (ICARD(1).EQ. ITHOLD8) GO TO 80  
ISN 0020      C      STORE CHARACTER IN WORD DESCRIBING SYMBOL, MAX OF 4 CHARACTERS  
ISN 0021      C      NDEX = NDEX + 1  
ISN 0022      C      IF (NDEX.GT. 4) GO TO 100  
ISN 0023      C      IF (ITHOLD(1).EQ. ICHAR(1))  
ISN 0024      C      GO TO 100  
ISN 0025      C      END OF SYMBOL  
ISN 0026      C      KOUNT = KOUNT + 1  
ISN 0027      C      ITEM(KOUNT) = ITHOLD8  
ISN 0028      C      NDEX = 0  
ISN 0029      C      DO 1 I = 1, 8  
ISN 0030      C      ITHOLD(I) = IBLNK1  
ISN 0031      C      CONTINUE  
ISN 0032      C      MOVSYM = KOUNT  
ISN 0033      C      RETURN  
ISN 0034      C      ENCL  
ISN 0035      C  
ISN 0036      C
```

*****F O R T R A N C R O S S R E F E R E N C E L I S T I N G*****

INTERNAL STATEMENT NUMBERS

SYMBOL	INTERNAL	STATEMENT NUMBERS
1	0000	0000
KOL	0001	0001
CARD	0002	0002
NDEX	0003	0003
ICARD	0004	0004
ITHOLD	0005	0005
ITEM	0006	0006
KOUNT	0007	0007
IBLNK1	0008	0008
ICARD	0009	0009
ITHOLD	0010	0010
MOVSYM	0011	0011
	0012	0012
	0013	0013
	0014	0014
	0015	0015
	0016	0016
	0017	0017
	0018	0018
	0019	0019
	0020	0020
	0021	0021
	0022	0022
	0023	0023
	0024	0024
	0025	0025
	0026	0026
	0027	0027
	0028	0028
	0029	0029
	0030	0030
	0031	0031
	0032	0032
	0033	0033
	0034	0034
	0035	0035
	0036	0036
	0037	0037
	0038	0038
	0039	0039
	0040	0040
	0041	0041
	0042	0042
	0043	0043
	0044	0044
	0045	0045
	0046	0046
	0047	0047
	0048	0048
	0049	0049
	0050	0050
	0051	0051
	0052	0052
	0053	0053
	0054	0054
	0055	0055
	0056	0056
	0057	0057
	0058	0058
	0059	0059
	0060	0060
	0061	0061
	0062	0062
	0063	0063
	0064	0064
	0065	0065
	0066	0066
	0067	0067
	0068	0068
	0069	0069
	0070	0070
	0071	0071
	0072	0072
	0073	0073
	0074	0074
	0075	0075
	0076	0076
	0077	0077
	0078	0078
	0079	0079
	0080	0080
	0081	0081
	0082	0082
	0083	0083
	0084	0084
	0085	0085
	0086	0086
	0087	0087
	0088	0088
	0089	0089
	0090	0090
	0091	0091
	0092	0092
	0093	0093
	0094	0094
	0095	0095
	0096	0096
	0097	0097
	0098	0098
	0099	0099
	0100	0100
	0101	0101
	0102	0102
	0103	0103
	0104	0104
	0105	0105
	0106	0106
	0107	0107
	0108	0108
	0109	0109
	0110	0110
	0111	0111
	0112	0112
	0113	0113
	0114	0114
	0115	0115
	0116	0116
	0117	0117
	0118	0118
	0119	0119
	0120	0120
	0121	0121
	0122	0122
	0123	0123
	0124	0124
	0125	0125
	0126	0126
	0127	0127
	0128	0128
	0129	0129
	0130	0130
	0131	0131
	0132	0132
	0133	0133
	0134	0134
	0135	0135
	0136	0136
	0137	0137
	0138	0138
	0139	0139
	0140	0140
	0141	0141
	0142	0142
	0143	0143
	0144	0144
	0145	0145
	0146	0146
	0147	0147
	0148	0148
	0149	0149
	0150	0150
	0151	0151
	0152	0152
	0153	0153
	0154	0154
	0155	0155
	0156	0156
	0157	0157
	0158	0158
	0159	0159
	0160	0160
	0161	0161
	0162	0162
	0163	0163
	0164	0164
	0165	0165
	0166	0166
	0167	0167
	0168	0168
	0169	0169
	0170	0170
	0171	0171
	0172	0172
	0173	0173
	0174	0174
	0175	0175
	0176	0176
	0177	0177
	0178	0178
	0179	0179
	0180	0180
	0181	0181
	0182	0182
	0183	0183
	0184	0184
	0185	0185
	0186	0186
	0187	0187
	0188	0188
	0189	0189
	0190	0190
	0191	0191
	0192	0192
	0193	0193
	0194	0194
	0195	0195
	0196	0196
	0197	0197
	0198	0198
	0199	0199
	0200	0200
	0201	0201
	0202	0202
	0203	0203
	0204	0204
	0205	0205
	0206	0206
	0207	0207
	0208	0208
	0209	0209
	0210	0210
	0211	0211
	0212	0212
	0213	0213
	0214	0214
	0215	0215
	0216	0216
	0217	0217
	0218	0218
	0219	0219
	0220	0220
	0221	0221
	0222	0222
	0223	0223
	0224	0224
	0225	0225
	0226	0226
	0227	0227
	0228	0228
	0229	0229
	0230	0230
	0231	0231
	0232	0232
	0233	0233
	0234	0234
	0235	0235
	0236	0236
	0237	0237
	0238	0238
	0239	0239
	0240	0240
	0241	0241
	0242	0242
	0243	0243
	0244	0244
	0245	0245
	0246	0246
	0247	0247
	0248	0248
	0249	0249
	0250	0250
	0251	0251
	0252	0252
	0253	0253
	0254	0254
	0255	0255
	0256	0256
	0257	0257
	0258	0258
	0259	0259
	0260	0260
	0261	0261
	0262	0262
	0263	0263
	0264	0264
	0265	0265
	0266	0266
	0267	0267
	0268	0268
	0269	0269
	0270	0270
	0271	0271
	0272	0272
	0273	0273
	0274	0274
	0275	0275
	0276	0276
	0277	0277
	0278	0278
	0279	0279
	0280	0280
	0281	0281
	0282	0282
	0283	0283
	0284	0284
	0285	0285
	0286	0286
	0287	0287
	0288	0288
	0289	0289
	0290	0290
	0291	0291
	0292	0292
	0293	0293
	0294	0294
	0295	0295
	0296	0296
	0297	0297
	0298	0298
	0299	0299
	0300	0300
	0301	0301
	0302	0302
	0303	0303
	0304	0304
	0305	0305
	0306	0306
	0307	0307
	0308	0308
	0309	0309
	0310	0310
	0311	0311
	0312	0312
	0313	0313
	0314	0314
	0315	0315
	0316	0316
	0317	0317
	0318	0318
	0319	0319
	0320	0320
	0321	0321
	0322	0322
	0323	0323
	0324	0324
	0325	0325
	0326	0326
	0327	0327
	0328	0328
	0329	0329
	0330	0330
	0331	0331
	0332	0332
	0333	0333
	0334	0334
	0335	0335
	0336	0336
	0337	0337
	0338	0338
	0339	0339
	0340	0340
	0341	0341
	0342	0342
	0343	0343
	0344	0344
	0345	0345
	0346	0346
	0347	0347
	0348	0348
	0349	0349
	0350	0350
	0351	0351
	0352	0352
	0353	0353
	0354	0354
	0355	0355
	0356	0356
	0357	0357
	0358	0358
	0359	0359
	0360	0360
	0361	0361
	0362	0362
	0363	0363
	0364	0364
	0365	0365
	0366	0366
	0367	0367
	0368	0368
	0369	0369
	0370	0370
	0371	0371
	0372	0372
	0373	0373
	0374	0374
	0375	0375
	0376	0376
	0377	0377
	0378	0378
	0379	0379
	0380	0380
	0381	0381
	0382	0382
	0383	0383
	0384	0384
	0385	0385
	0386	0386
	0387	0387
	0388	0388
	0389	0389
	0390	0390
	0391	0391
	0392	0392
	0393	0393
	0394	0394
	0395	0395
	0396	0396
	0397	0397
	0398	0398
	0399	0399
	0400	0400
	0401	0401
	0402	0402
	0403	0403
	0404	0404
	0405	0405
	0406	0406
	0407	0407
	0408	0408
	0409	0409
	0410	0410
	0411	0411
	0412	0412
	0413	0413
	0414	0414
	0415	0415
	0416	0416
	0417	0417
	0418	0418
	0419	0419
	0420	0420
	0421	0421
	0422	0422
	0423	0423
	0424	042

ORIGINAL PAGE IS
OF POOR QUALITY

PAGE 2

DATE 01.141/14.02.14

OS/360 FORTRAN H EXTENDED

NUMRFL

LEVEL 2.3.0 (JUNE 78)

LISTING G*****

CROSS REFERENCE

NUMRFL

LEVEL 2.3.0 (JUNE 78)

INTERNAL STATEMENT NUMBERS 0049 0049 0050 0051

NUMRFL 0026 0026 0031 0040 0044 0050

NUMRFL 0005 0018 0020 0043 0047

NUMRFL 0007 0022 0026 0030

NUMRFL 0004 0028 0032 0035

NUMRFL 0030 0032 0035

NUMRFL 0031 0032 0035

NUMRFL 0031 0032 0035

NUMRFL 0031 0032 0035

NUMRFL 0031 0032 0035

NUMRFL 0031 0032 0035

NUMRFL 0031 0032 0035

NUMRFL 0031 0032 0035

NUMRFL 0031 0032 0035

NUMRFL 0031 0032 0035

NUMRFL 0031 0032 0035

NUMRFL 0031 0032 0035

NUMRFL 0031 0032 0035

NUMRFL 0031 0032 0035

NUMRFL 0031 0032 0035

NUMRFL 0031 0032 0035

NUMRFL 0031 0032 0035

NUMRFL 0031 0032 0035

NUMRFL 0031 0032 0035

NUMRFL 0031 0032 0035

NUMRFL 0031 0032 0035

NUMRFL 0031 0032 0035

NUMRFL 0031 0032 0035

NUMRFL 0031 0032 0035

NUMRFL 0031 0032 0035

NUMRFL 0031 0032 0035

NUMRFL 0031 0032 0035

NUMRFL 0031 0032 0035

NUMRFL 0031 0032 0035

NUMRFL 0031 0032 0035

NUMRFL 0031 0032 0035

NUMRFL 0031 0032 0035

NUMRFL 0031 0032 0035

NUMRFL 0031 0032 0035

NUMRFL 0031 0032 0035

NUMRFL 0031 0032 0035

NUMRFL 0031 0032 0035

NUMRFL 0031 0032 0035

NUMRFL 0031 0032 0035

NUMRFL 0031 0032 0035

NUMRFL 0031 0032 0035

NUMRFL 0031 0032 0035

NUMRFL 0031 0032 0035

NUMRFL 0031 0032 0035

NUMRFL 0031 0032 0035

NUMRFL 0031 0032 0035

NUMRFL 0031 0032 0035

NUMRFL 0031 0032 0035

NUMRFL 0031 0032 0035

NUMRFL 0031 0032 0035

NUMRFL 0031 0032 0035

NUMRFL 0031 0032 0035

NUMRFL 0031 0032 0035

NUMRFL 0031 0032 0035

NUMRFL 0031 0032 0035

NUMRFL 0031 0032 0035

NUMRFL 0031 0032 0035

NUMRFL 0031 0032 0035

NUMRFL 0031 0032 0035

NUMRFL 0031 0032 0035

NUMRFL 0031 0032 0035

NUMRFL 0031 0032 0035

NUMRFL 0031 0032 0035

NUMRFL 0031 0032 0035

NUMRFL 0031 0032 0035

NUMRFL 0031 0032 0035

NUMRFL 0031 0032 0035

NUMRFL 0031 0032 0035

NUMRFL 0031 0032 0035

NUMRFL 0031 0032 0035

NUMRFL 0031 0032 0035

NUMRFL 0031 0032 0035

NUMRFL 0031 0032 0035

NUMRFL 0031 0032 0035

NUMRFL 0031 0032 0035

NUMRFL 0031 0032 0035

NUMRFL 0031 0032 0035

NUMRFL 0031 0032 0035

ORIGINAL PAGE IS
OF POOR QUALITY

DATE 81.141/14.17.41

05/360 FORTKAM H EXTENDED

*LEVEL 2.3.0 (JUNE 78)

REQUESTED OPTIONS: NO TERM

OPTIONS IN EFFECT: NAME(MAIN) OPTIMIZE(1) LINECOUNT(80) SIZE(MAX) AUTOORL(NONE)
SOURCE EBCDIC NOLIST NOCHECK OBJECT MAP NOFORMAT NOGOSYMT XREF ALC NOANSF NOTERM IBM FLAG(1)

```

ISN 0902 SUBROUTINE RDEKEC
ISN 0903 IMPLICIT INTEGER (A-X)

PURPOSE: READ INFORMATION FROM THE EXEC FILE AND THE LARS DIRECTORY
          INFORMATION WRITTEN ON FILE 7 BY THE PROGRAM
          SEGMENT NUMBER
          NUMBER OF ACQUISITIONS
          ACQUISITION DATES
          SUN ANGLES
          LANDSAT NUMBERS

COMMON /USER/ ICROP(4),ZX(4),SUNANG(8)
REAL *4 ZX
COMMON /MISC/ NOACO, ACQDT(8), KSEGM, DATE(4),LANDST(8)
REAL *4 ACQDT

C READ SEGMENT NUMBER
CCCC WRITE (3,9999)
9999 FORMAT (' ENTERING RDEKEC.')
1000 READ (7,1000) KSEGM
1000 FORMAT (20A4)
C
CCCC WRITE (3,9998) KSEGM
9998 FORMAT (' KSEGM=',A4)
C READ NUMBER OF ACQUISITIONS
CCCC READ (7,400) NOACO
400 FORMAT (20I4)
C
C READ ACQUISITION DATE
CCCC READ (7,700) (ACQDT(I),I=1,NOACO)
700 FORMAT (10I2X,A5)
C
C READ SUN ANGLES
CCCC READ (7,400) (SUNANG(I),I=1,NOACO)
C
C READ LANDSAT NUMBERS
CCCC READ (7,400) (LANDST(I),I=1,NOACO)
CCCC WRITE (3,400) (LANDST(I),I=1,NOACO)
C
RETURN
END

```

*****F O R T R A N C R O S S R E F E R E N C E L I S T I N G*****

INTERNAL STATEMENT NUMBERS
 0014 0016 0016 0016 0016 0017 0017 0017

ZX 0004 0005 0007 0014
 ACQDT 0006 0007 0014
 ICROP 0006 0007 0014
 KSEGM 0006 0007 0014
 NOACO 0006 0007 0014
 LANDST 0006 0007 0014
 RDEKEC 0004 0016

*****F O R T R A N C R O S S R E F E R E N C E L I S T I N G*****

LABEL 0013 0015 0016 0017
 400 0013 0015 0016 0017
 700 0013 0015 0016 0017
 1000 0013 0015 0016 0017
 9998 0013 0015 0016 0017
 9999 0013 0015 0016 0017

NAME		TAG	TYPE	ADD.	NAME	TAG	TYPE	ADD.	NAME	TAG	TYPE	ADD.	NAME	TAG	TYPE	ADD.	NAME	TAG	TYPE	ADD.
I	F		I+4	0000HC	ZK	C	R+4	NR	DATE	C	I+4	NR	ACQD	S	C	M+8	000008			

*LEVEL 2.3.0 (JUNE 78) RDEEXEC OS/360 FORTRAN H EXTENDED DATE 81.141/14.17.41 PAGE 2
 ICROP C 104 NR KSEGH S C 104 000048 NOACO SF C 104 000000 10COMB F XF 104 000000
 LANDSY S C 104 NR RDEEXEC 00005C 000000 SUNANG S C 104 000020 000020

***** COMMON INFORMATION *****

NAME OF COMMON BLOCK * USER* SIZE OF BLOCK 000048 HEXADECIMAL BYTES
 VAR NAME TYPE REL ADDR VAR NAME TYPE REL ADDR VAR NAME TYPE REL ADDR
 ICROP 104 000000 NR 2X 104 000010 NR SUNANG 104 000020

NAME OF COMMON BLOCK * MISC* SIZE OF BLOCK 00007C HEXADECIMAL BYTES
 VAR NAME TYPE REL ADDR VAR NAME TYPE REL ADDR VAR NAME TYPE REL ADDR
 NOACO 104 000000 000000 ACOUT 104 000000 KSEGH 104 000048 VAR DATE 104 00004C NR
 LANDSY 104 00005C

COMPILER GENERATED LABELS

LABEL	ISN	ADDR	LABEL	ISN	ADDR
100001	2	00005C			

FORMAT STATEMENT LABELS

LABEL	ISN	ADDR	LABEL	ISN	ADDR
9979	10	00003C	400	13	00004F
780	15	000055			

*OPTIONS IN EFFECT*NAME(MAIN) OPTIMIZE(1) LINECOUNT(80) SIZE(MAX) AUTOOBL(NONE)
 *OPTIONS IN EFFECT*SOURCE EBCDIC NOLIST NODECK OBJECT MAP MFORMAT NOGOSTMT XREF ALC NOANSF NOTERM IBM FLAG(1)
 STATISTICS SOURCE STATEMENTS = 18, PROGRAM SIZE = 458, SUBPROGRAM NAME =RDEEXEC

STATISTICS NO DIAGNOSTICS GENERATED

***** END OF COMPILATION *****

296K BYTES OF CORE NOT USED

ORIGINAL PAGE IS
 OF POOR QUALITY

REQUESTED OPTIONS: NOTERM
OPTIONS IN EFFECT:

ISN 0002 SURROUTINE ROLES (ITYPE, HDR, VERTPX, VERTLN, IERROR)
PURPOSE: MOVE DATA FROM A UNIVERSAL FORMAT TAPE TO IDATA
MOVE MULTIPLE CHANNELS OF DATA

***** INPUT *****
DATA FILES ON UNITS 11 - 18
***** OUTPUT *****
ITYPE = 1 READ HEADER RECORDS AND POSITION TAPE FOR 1ST FILE
ITYPE = 2 READ A LINE OF PIXELS INTO IDATA
RADIANCE VALUES (196 X NUMBER OF CHANNELS)

IMPLICIT INTEGER (A-Z)
LOGICAL*1 HDR(1)
REAL*4 VERTPX(4), VERTLN(4)

IDATA HAS (72 * 4 * 196) CHARACTERS FOR A MAX OF 8 ACQUISITIONS
COMMON /LINES/ NATLNE, LINE NO, IDATA(856,8), NOACQS
LOGICAL*1 IDATA

ITYPE=1 READ HEADER; ITYPE=2, READ DATA
IF ITYPE .EQ. 2) GO TO 100

SKIP OVER HEADER RECORDS
DO 15 I=1, NOACQS
ATAPE=10
READ (ITAPE, 1111, END=901) HDR
FORMAT (17(180A11))
CONTINUE

NOFLD=0
READ FIELD DEFINITION
CALL MOVFRT (VERTPX, VERTLN, IERROR)
SAMPLING = 1
LINING = 1
WRITE (6,1600) SAMPLING, LINING, (VERTPX(I), VERTLN(I), I=1,4)
FORMAT (/,/, PIXEL SKIP FACTOR = ,14,/, LINE SKIP FACTOR = ,14,/,
/, VERTICES (PIXEL, LINE)=,5(11,F4.0,/,F4.0,/,),IX)

SET NEXT LINE NUMBER
NATLNE = 1
RETURN

NO FILE = ITAPE - 10
WRITE (6,902) IDISK
WRITE (3,902) IDISK
FORMAT (/, DISK FILE HEADER RECORD FOR FILE ,12, * IS MISSING.,
/, IERROR = 1
RETURN

READ LINES FROM RADIANCE VALUE FILES
SKIP OVER UNDEFINED LINES
IF (NATLNE .EQ. LINE NO) GO TO 120

ISKIP = LINE NO - NATLNE
DO 110 J=1, NOACQS
ITAPE = 10 + J
DO 110 I=1, ISKIP
READ (ITAPE, 1111, END=910) DUMMY
CONTINUE

DO 130 I=1, NOACQS
ITAPE = 10 + I
READ (ITAPE, 4*196) CHARACTERS

ORIGINAL PAGE IS
OF POOR QUALITY

RDF00010
RDF00020
RDF00030
RDF00040
RDF00050
RDF00060
RDF00070
RDF00080
RDF00090
RDF00100
RDF00110
RDF00120
RDF00130
RDF00140
RDF00150
RDF00160
RDF00170
RDF00180
RDF00190
RDF00200
RDF00210
RDF00220
RDF00230
RDF00240
RDF00250
RDF00260
RDF00270
RDF00280
RDF00290
RDF00300
RDF00310
RDF00320
RDF00330
RDF00340
RDF00350
RDF00360
RDF00370
RDF00380
RDF00390
RDF00400
RDF00410
RDF00420
RDF00430
RDF00440
RDF00450
RDF00460
RDF00470
RDF00480
RDF00490
RDF00500
RDF00510
RDF00520
RDF00530
RDF00540
RDF00550
RDF00560
RDF00570
RDF00580
RDF00590
RDF00600
RDF00610
RDF00620
RDF00630
RDF00640
RDF00650
RDF00660
RDF00670
RDF00680
RDF00690
RDF00700
RDF00710
RDF00720
RDF00730

DATE 81.141/14.18.02
REL: AMR. VAR: NAM
000000 NOACQS

FORTRAN M EXTENDED
REL. ADDR. VAR. IN

TYPE
104
09C/50

PROFILES
AND

2.3.0 (JAN 76)	VAR.	NAMF	TYPE
	NXTLINE	104	

LEVEL

SOURCE STATEMENT LABELS

LABEL	IS/I	ADDR
10	9	00024A
100	71	000380
910	46	00043A

COMPILER GENERATED LABELS

LABEL	ISN	ADDR
000001	2	000220
000005	14	000280
000009	33	00038C
000013	39	0003CE
000020	44	000420

FORMAT STATEMENT LABELS

LARFL	ISN	ADDR
11111	15	060028
911	40	0000EA

OPTIONS IN EFFECT*NAME(MAIN) OPTIMIZE(1) LINECOUNT(80) SIZE(MAX) AUTOORL(NONE)

```

OPTIONS IN FFFCT*SOURCE FBDCIC NOLIST NODECK OBJECT MAP I:FORMAT NOGOSTNT XREF ALC NOANSF NOTERM IBM FLAG(I)

```

```

*STATISTICS* SOURCE STATEMENTS = 51, PROGRAM SIZE = 1322, SUBPROGRAM NAME =RDFILES

```

STATISTICS • NO DIAGNOSTICS GENERATED

***** END OF COMPILATION *****

292K BYTES OF CORE NOT USED

REQUESTED OPTIONS: NOTERM

OPTIONS IN EFFECT: NAME(MAIN) OPTIMIZE(1) LINECOUNT(80) SIZE(4) AUTODIR(NONE)
SOURCE EHCDC NOLIST NODECK OBJECT MAP NOFORMAT NOGOSMT AREF AL NOANSF NOTERM IBM FLAG(1)

```

ISN 0002      CCCCCCCCCC
              SURROUTINE NOVERT (VERIPX, VERTLN, IERROR)
              PURPOSE--READ AND DECODE A CARD DESCRIBING VERTICES OF TRAINING OR
              TEST FIELD. CARD CAN BE ABSENT INDICATING COMPLETE
              FIELD OR CARD CAN BE IN THE FOLLOWING FORMAT:
              (1,1), (X1,Y1), (X2,Y2), (X3,Y3), (X4,Y4)
              WHERE X1,Y1 IS THE UPPER LEFT CORNER AND THE VERTICES
              CONTINUE IN A CLOCKWISE DIRECTION.
              IMPLICIT INTEGER(A-Z)
              INTEGER CARD(80)
              REAL *4 VERIPX(4), VERTLN(4)
              DATA *4 XDEF(4), YDEF(4)
              DATA BLANK//, COMMA//, OPNPAR//, CLSPAR//,
              DATA XDEF(1), YDEF(1), XDEF(2), YDEF(2), XDEF(3), YDEF(3), XDEF(4), YDEF(4)
              C
              C READ CARD
              READ(2, 6, END=990) CARD
              FORMAT(A41)
              C
              C SET PROGRAM TO NO COLUMNS READ, NO VERTICES FOUND
              NOCOL=0
              NOVERT = -1
              C
              C SET SWITCH TO NO PIXEL NUMBER READ
              IPIXEL = 0
              C
              C FIRST NON-BLANK CHARACTER MUST BE A (
              IF (CHAR=NUMCHR(CARD,NOCOL) GO TO 935
              IF (CHAR=EQ, BLANK) GO TO 935
              IF (CHAR=NE, OPNPAR) GO TO 903
              NUM=0
              IF (CHAR=NUMCHR(CARD,NOCOL)
              IF (CHAR=EQ, BLANK) GO TO 935
              C
              C CHECK FOR COMMA SEPARATING PIXEL, LINE
              IF (CHAR=EQ, COMMA) GO TO 8
              C
              C CHECK FOR RIGHT PARENTHESIS FINISHING PIXEL-LINE COMPLET
              IF (CARD(NOCOL).EQ, CLSPAR, GO TO 8
              C
              C CHARACTER MUST BE NUMERIC
              CALL I4A1N(CHAR), NUMCHR
              IF (NUMCHR.L1, 0).DA, (NUMCHR.GT, 9)) GO TO 903
              C
              C NUMERIC CHARACTER, CONVERT TO COMPUTATIONAL NUMBER AND INCLUDE IN SUM
              NUM=10*NUM+NUMCHR
              GO TO 4
              C
              C VERTEX PIXEL NUMBER
              NOVERT = NOVERT + 1
              IF (NOVERT.GT, 4) GO TO 910
              IF (IPIXEL.NE, 0) GO TO 903
              IF (NUM.GT, 9) GO TO 903
              IF (NUM.GT, 9) GO TO 903
              IF (NOVERT.GT, 0) VERIPX(NOVERT) = NUM
              IF (IPIXEL.NE, 0)
              GO TO 3
              C
              C VERTEX LINE NUMBER
              IF (IPIXEL.EQ, 0) GO TO 903
              IF (NUM.GT, 9) GO TO 903
              IF (NOVERT.GT, 0) VERTLN(NOVERT) = NUM
              C
              C CHECK FOR COMMA FOLLOWING (PIXEL-LINE)
              IF (CHAR=NUMCHR(CARD,NOCOL)
              IF (CHAR=EQ, BLANK) GO TO 930
              IF (CHAR=EQ, COMMA) GO TO 2
              C

```

ORIGINAL PAGE IS
OF POOR QUALITY.

ORIGINAL PAGE IS
OF POOR QUALITY

DATE 81.141/14.18.07

05/360 FORTRAN M EXTENDED

ROVERT

LEVEL 2.3.0 (LJMF 78)

```

C SOMETHING WRONG WITH ORDER OF CHARACTERS
ISN 0055
ISN 0056
ISN 0057
ISN 0058
ISN 0059
ISN 0060
ISN 0061
ISN 0062
ISN 0063
ISN 0064
ISN 0065
ISN 0066
ISN 0067
ISN 0068
ISN 0069
ISN 0070
ISN 0071
ISN 0072
ISN 0073
ISN 0074
ISN 0075
ISN 0076
ISN 0077

C 903 WRITE (6,904) CARD
C 904 FORMAT(' ERROR IN VERTICES CARD',/,IX,80A1,/,) RUN WILL TERMINATE
C 905 IERROR = 1
C 906 RETURN
C 907
C 908 WRITE (6,909) CARD
C 909 WRITE (6,910) CARD
C 910 FORMAT(' ERROR IN VERTICES CARD',/,IX,80A1,/,) RUN WILL TERMINATE
C 911 IERROR = 1
C 912 RETURN
C 913
C 914 END OF CARD
C 915 IF (NOVERT .EQ. 4) RETURN
C 916
C 917 ERROR CARD TERMINATES BEFORE 4TH VERTICES FINISHED
C 918 WRITE (6,919) CARD
C 919 WRITE (6,920) CARD
C 920 FORMAT(' ERROR IN VERTICES CARD',/,IX,80A1,/,) RUN WILL TERMINATE
C 921 IERROR = 1
C 922 RETURN
C 923
C 924 NO FIELD DEFINITION CARD, DEFAULT TO WHOLE SCENE
C 925 DO 926 I = 1, 4
C 926 VERTX(I) = XDEFLT(I)
C 927 VERTY(I) = YDEFLT(I)
C 928 CONTINUE
C 929 RETURN
C 930
C 931
C 932
C 933
C 934
C 935
C 936
C 937
C 938
C 939
C 940
C 941
C 942
C 943
C 944
C 945
C 946
C 947
C 948
C 949
C 950
C 951
C 952
C 953
C 954
C 955
C 956
C 957
C 958
C 959
C 960
C 961
C 962
C 963
C 964
C 965
C 966
C 967
C 968
C 969
C 970
C 971
C 972
C 973
C 974
C 975
C 976
C 977
C 978
C 979
C 980
C 981
C 982
C 983
C 984
C 985
C 986
C 987
C 988
C 989
C 990
C 991
C 992
C 993
C 994
C 995
C 996
C 997
C 998
C 999

```

***** REFERENCE LISTING *****

SYMBOL	INTERNAL	STATEMENT	NUMBERS	CROSS	REFERENCE	LISTING
NUM	0072	0073	0074	0042	0048	0068
CARD	0075	0076	0077	0043	0049	0069
BLANK	0078	0079	0080	0044	0050	0070
CHAR	0081	0082	0083	0045	0051	0071
NOCOL	0084	0085	0086	0046	0052	0072
CLSPAR	0087	0088	0089	0047	0053	0073
PICTEL	0090	0091	0092	0048	0054	0074
NOVERT	0093	0094	0095	0049	0055	0075
NUMCHR	0096	0097	0098	0050	0056	0076
NATCHR	0099	0100	0101	0051	0057	0077
OPNPAR	0102	0103	0104	0052	0058	0078
ADVERT	0105	0106	0107	0053	0059	0079
VERTX	0108	0109	0110	0054	0060	0080
YDEFLT	0111	0112	0113	0055	0061	0081

***** REFERENCE LISTING *****

LABEL	DEFINED	REFERENCES	CROSS	REFERENCE	LISTING
3	0014	0053	0044	0046	0068
4	0015	0054	0045	0047	0069
5	0016	0055	0046	0048	0070
6	0017	0056	0047	0049	0071
7	0018	0057	0048	0050	0072
8	0019	0058	0049	0051	0073
9	0020	0059	0050	0052	0074
10	0021	0060	0051	0053	0075
11	0022	0061	0052	0054	0076
12	0023	0062	0053	0055	0077
13	0024	0063	0054	0056	0078
14	0025	0064	0055	0057	0079
15	0026	0065	0056	0058	0080
16	0027	0066	0057	0059	0081
17	0028	0067	0058	0060	0082
18	0029	0068	0059	0061	0083
19	0030	0069	0060	0062	0084
20	0031	0070	0061	0063	0085
21	0032	0071	0062	0064	0086
22	0033	0072	0063	0065	0087
23	0034	0073	0064	0066	0088
24	0035	0074	0065	0067	0089
25	0036	0075	0066	0068	0090
26	0037	0076	0067	0069	0091
27	0038	0077	0068	0070	0092
28	0039	0078	0069	0071	0093
29	0040	0079	0070	0072	0094
30	0041	0080	0071	0073	0095
31	0042	0081	0072	0074	0096
32	0043	0082	0073	0075	0097
33	0044	0083	0074	0076	0098
34	0045	0084	0075	0077	0099
35	0046	0085	0076	0078	0100
36	0047	0086	0077	0079	0101
37	0048	0087	0078	0080	0102
38	0049	0088	0079	0081	0103
39	0050	0089	0080	0082	0104
40	0051	0090	0081	0083	0105
41	0052	0091	0082	0084	0106
42	0053	0092	0083	0085	0107
43	0054	0093	0084	0086	0108
44	0055	0094	0085	0087	0109
45	0056	0095	0086	0088	0110
46	0057	0096	0087	0089	0111
47	0058	0097	0088	0090	0112
48	0059	0098	0089	0091	0113
49	0060	0099	0090	0092	0114
50	0061	0100	0091	0093	0115
51	0062	0101	0092	0094	0116
52	0063	0102	0093	0095	0117
53	0064	0103	0094	0096	0118
54	0065	0104	0095	0097	0119
55	0066	0105	0096	0098	0120
56	0067	0106	0097	0099	0121
57	0068	0107	0098	0100	0122
58	0069	0108	0099	0101	0123
59	0070	0109	0100	0102	0124
60	0071	0110	0101	0103	0125
61	0072	0111	0102	0104	0126
62	0073	0112	0103	0105	0127
63	0074	0113	0104	0106	0128
64	0075	0114	0105	0107	0129
65	0076	0115	0106	0108	0130
66	0077	0116	0107	0109	0131
67	0078	0117	0108	0110	0132
68	0079	0118	0109	0111	0133
69	0080	0119	0110	0112	0134
70	0081	0120	0111	0113	0135
71	0082	0121	0112	0114	0136
72	0083	0122	0113	0115	0137
73	0084	0123	0114	0116	0138
74	0085	0124	0115	0117	0139
75	0086	0125	0116	0118	0140
76	0087	0126	0117	0119	0141
77	0088	0127	0118	0120	0142
78	0089	0128	0119	0121	0143
79	0090	0129	0120	0122	0144
80	0091	0130	0121	0123	0145
81	0092	0131	0122	0124	0146
82	0093	0132	0123	0125	0147
83	0094	0133	0124	0126	0148
84	0095	0134	0125	0127	0149
85	0096	0135	0126	0128	0150
86	0097	0136	0127	0129	0151
87	0098	0137	0128	0130	0152
88	0099	0138	0129	0131	0153
89	0100	0139	0130	0132	0154
90	0101	0140	0131	0133	0155
91	0102	0141	0132	0134	0156
92	0103	0142	0133	0135	0157
93	0104	0143	0134	0136	0158
94	0105	0144	0135	0137	0159
95	0106	0145	0136	0138	0160
96	0107	0146	0137	0139	0161
97	0108	0147	0138	0140	0162
98	0109	0148	0139	0141	0163
99	0110	0149	0140	0142	0164
100	0111	0150	0141	0143	0165
101	0112	0151	0142	0144	0166
102	0113	0152	0143	0145	0167
103	0114	0153	0144	0146	0168
104	0115	0154	0145	0147	0169
105	0116	0155	0146	0148	0170
106	0117	0156	0147	0149	0171
107	0118	0157	0148	0150	0172
108	0119	0158	0149	0151	0173
109	0120	0159	0150	0152	0174
110	0121	0160	0151	0153	0175
111	0122	0161	0152	0154	0176
112	0123	0162	0153	0155	0177
113	0124	0163	0154	0156	0178
114	0125	0164	0155	0157	0179
115	0126	0165	0156	0158	0180
116	0127	0166	0157	0159	0181
117	0128	0167	0158	0160	0182
118	0129	0168	0159	0161	0183
119	0130	0169	0160	0162	0184
120	0131	0170	0161	0163	0185
121	0132	0171	0162	0164	0186
122	0133	0172	0163	0165	0187
123	0134	0173	0164	0166	0188
124	0135	0174	0165	0167	0189
125	0136	0175	0166	0168	0190
126	0137	0176	0167	0169	0191
127	0138	0177	0168	0170	0192
128	0139	0178	0169	0171	0193
129	0140	0179	0170	0172	0194
130	0141	0180	0171	0173	0195
131	0142	0181	0172	0174	0196
132	0143	0182	0173	0175	0197
133	0144	0183	0174	0176	0198
134	0145	0184	0175	0177	0199
135	0146	0185	0176	0178	0200
136	0147	0186	0177	0179	0201
137	0148	0187	0178	0180	0202
138	0149	0188	0179	0181	0203
139	0150	0189	0180	0182	0204
140	0151	0190	0181	0183	0205
141	0152	0191	0182	0184	0206
142	0153	0192	0183	0185	0207
143	0154	0193	0184	0186	0208
144	0155	0194	0185	0187	0209
145	0156	0195	0186	0188	0210
146	0157	0196	0187	0189	0211
147	0158	0197	0188	0190	0212
148	0159	0198	0189	0191	0213
149	0160	0199	0190	0192	0214
150	0161	0200	0191	0193	0215
151	0162	0201	0192	0194	0216

ORIGINAL PAGE IS
OF POOR QUALITY

PAGE 1

DATE 01.141/14.19.35

OS/360 FORTRAN H EXTENDED

LEVEL 2.3.0 (JUNE 78)

REQUESTED OPTIONS: NOTERM

OPTIONS IN EFFECT: NAME(MAIN) OPTIMIZE(1) INECOUNT(80) SIZE(MAX) AUTODIAG(NONE)
SOURCE EBCDIC NOLIST NOBACK OBJECT MAP NOFORMAT NOGOSYNT XREF ALC NOANSF NOTERM IBM FLAG(1)

```
ISN 0002      C      SURROUTINE RECT (P,Q,XX,XY,ICOR)
ISN 0003      C      PURPOSE: DETERMINE IF POINT IS IN TRAINING FIELD
ISN 0004      C      DIMENSION XX(14),XY(14),THETA(4),AM(4),A,(4),AY(4)
ISN 0005      C      ICOR=1
ISN 0006      C      NN=4
ISN 0007      C      DO 4 M=1,NN
ISN 0008      C      IF (P.EQ.XX(M) .AND. Q.EQ.XY(M)) GO TO 5
ISN 0009      C      CONTINUE
ISN 0010      C      GO TO 6
ISN 0011      C      POINT IN BOUNDS
ISN 0012      C      ICOR = 0
ISN 0013      C      RETURN
ISN 0014      C      CHECK FOR POINT INSIDE OF BOUNDS
ISN 0015      C      DO 1 I=1,NN
ISN 0016      C      AX(I) = P - XX(I)
ISN 0017      C      AY(I) = Q - XY(I)
ISN 0018      C      ZN=AX(I)*AX(I)+AY(I)*AY(I)
ISN 0019      C      AM(I) = SQRT(ZN)
ISN 0020      C      DO 2 J=1,NN
ISN 0021      C      K=J+1
ISN 0022      C      IF (K.GT.NN) K=1
ISN 0023      C      THETA(J)=AX(K)*AY(J)/(AM(J)*AM(K))
ISN 0024      C      THETA(J) = ACOS(ATH)
ISN 0025      C      SUM = 0
ISN 0026      C      DO 3 L=1,NN
ISN 0027      C      SUM = SUM+THETA(L)
ISN 0028      C      DIFF = SUM - 3.141592634*2.
ISN 0029      C      IF (DIFF.LE.1.E-04) ICOR = 0
ISN 0030      C      RETURN
ISN 0031      C      END
ISN 0032      C
ISN 0033      C
```

*****FORTRAN CROSS REFERENCE LISTING*****

SYMBOL	INTERNAL STATEMENT NUMBERS	CROSS REFERENCE
J	0014	0016 0016 0017
K	0019	0016 0016 0017
L	0020	0016 0016 0017
M	0026	0016 0016 0017
P	0007	0016 0016 0017
Q	0007	0016 0016 0017
XX	0007	0016 0016 0017
XY	0007	0016 0016 0017
AM	0007	0016 0016 0017
AY	0007	0016 0016 0017
NN	0005	0016 0016 0017
ICOR	0005	0016 0016 0017
THETA	0023	0016 0016 0017

SYMBOL	INTERNAL STATEMENT NUMBERS	CROSS REFERENCE
J	0014	0016 0016 0017
K	0019	0016 0016 0017
L	0020	0016 0016 0017
M	0026	0016 0016 0017
P	0007	0016 0016 0017
Q	0007	0016 0016 0017
XX	0007	0016 0016 0017
XY	0007	0016 0016 0017
AM	0007	0016 0016 0017
AY	0007	0016 0016 0017
NN	0005	0016 0016 0017
ICOR	0005	0016 0016 0017
THETA	0023	0016 0016 0017

SYMBOL	INTERNAL STATEMENT NUMBERS	CROSS REFERENCE
J	0014	0016 0016 0017
K	0019	0016 0016 0017
L	0020	0016 0016 0017
M	0026	0016 0016 0017
P	0007	0016 0016 0017
Q	0007	0016 0016 0017
XX	0007	0016 0016 0017
XY	0007	0016 0016 0017
AM	0007	0016 0016 0017
AY	0007	0016 0016 0017
NN	0005	0016 0016 0017
ICOR	0005	0016 0016 0017
THETA	0023	0016 0016 0017

*****FORTRAN REFERENCES*****

DEFINER	REFERENCES
0017	0013
0023	0018
0025	0025
0026	0026
0027	0027
0028	0028
0029	0029
0030	0030
0031	0031
0032	0032

LEVEL 2.3.0 (NAME 7M)	REFCT	05/360	FORTRAN W EXTENDED		DATE 81.141/14.19.35	PAGE 2
NAME	TYPE	ADD.	NAME	TYPE	ADD.	TYPE
I	I	0000A4	J	I	0000A4	I
M	I	0000A4	F	I	0000A4	I
A	I	0000A4	F	I	0000A4	I
X	I	0000EC	A	I	0000EC	I
X	I	0000E0	S	I	0000E0	I
A	I	0000E0	F	I	0000E0	I
C	I	0000E0	F	I	0000E0	I
S	I	0000E0	F	I	0000E0	I
O	I	0000E0	F	I	0000E0	I
R	I	0000E0	F	I	0000E0	I
T	I	0000E0	F	I	0000E0	I
S	I	0000E0	F	I	0000E0	I
O	I	0000E0	F	I	0000E0	I
R	I	0000E0	F	I	0000E0	I
T	I	0000E0	F	I	0000E0	I
S	I	0000E0	F	I	0000E0	I
O	I	0000E0	F	I	0000E0	I
R	I	0000E0	F	I	0000E0	I
T	I	0000E0	F	I	0000E0	I
S	I	0000E0	F	I	0000E0	I
O	I	0000E0	F	I	0000E0	I
R	I	0000E0	F	I	0000E0	I
T	I	0000E0	F	I	0000E0	I
S	I	0000E0	F	I	0000E0	I
O	I	0000E0	F	I	0000E0	I
R	I	0000E0	F	I	0000E0	I
T	I	0000E0	F	I	0000E0	I
S	I	0000E0	F	I	0000E0	I
O	I	0000E0	F	I	0000E0	I
R	I	0000E0	F	I	0000E0	I
T	I	0000E0	F	I	0000E0	I
S	I	0000E0	F	I	0000E0	I
O	I	0000E0	F	I	0000E0	I
R	I	0000E0	F	I	0000E0	I
T	I	0000E0	F	I	0000E0	I
S	I	0000E0	F	I	0000E0	I
O	I	0000E0	F	I	0000E0	I
R	I	0000E0	F	I	0000E0	I
T	I	0000E0	F	I	0000E0	I
S	I	0000E0	F	I	0000E0	I
O	I	0000E0	F	I	0000E0	I
R	I	0000E0	F	I	0000E0	I
T	I	0000E0	F	I	0000E0	I
S	I	0000E0	F	I	0000E0	I
O	I	0000E0	F	I	0000E0	I
R	I	0000E0	F	I	0000E0	I
T	I	0000E0	F	I	0000E0	I
S	I	0000E0	F	I	0000E0	I
O	I	0000E0	F	I	0000E0	I
R	I	0000E0	F	I	0000E0	I
T	I	0000E0	F	I	0000E0	I
S	I	0000E0	F	I	0000E0	I
O	I	0000E0	F	I	0000E0	I
R	I	0000E0	F	I	0000E0	I
T	I	0000E0	F	I	0000E0	I
S	I	0000E0	F	I	0000E0	I
O	I	0000E0	F	I	0000E0	I
R	I	0000E0	F	I	0000E0	I
T	I	0000E0	F	I	0000E0	I
S	I	0000E0	F	I	0000E0	I
O	I	0000E0	F	I	0000E0	I
R	I	0000E0	F	I	0000E0	I
T	I	0000E0	F	I	0000E0	I
S	I	0000E0	F	I	0000E0	I
O	I	0000E0	F			

SOURCE STATEMENT LABELS

LABEL	ISN	ANTR
4	9	000194
2	21	000079E

COMPILER GENERATED LABELS

Label	1	2	3	4	5	6	7	8	9	10	11	12	13	14	15	16	17	18	19	20	21	22	23	24	25	26	27	28	29	30	31	32	33	34	35	36	37	38	39	40	41	42	43	44	45	46	47	48	49	50	51	52	53	54	55	56	57	58	59	60	61	62	63	64	65	66	67	68	69	70	71	72	73	74	75	76	77	78	79	80	81	82	83	84	85	86	87	88	89	90	91	92	93	94	95	96	97	98	99	100																																																																																																																																																																												
ANR	000140	000141	000142	000143	000144	000145	000146	000147	000148	000149	000150	000151	000152	000153	000154	000155	000156	000157	000158	000159	000160	000161	000162	000163	000164	000165	000166	000167	000168	000169	000170	000171	000172	000173	000174	000175	000176	000177	000178	000179	000180	000181	000182	000183	000184	000185	000186	000187	000188	000189	000190	000191	000192	000193	000194	000195	000196	000197	000198	000199	000200	000201	000202	000203	000204	000205	000206	000207	000208	000209	000210	000211	000212	000213	000214	000215	000216	000217	000218	000219	000220	000221	000222	000223	000224	000225	000226	000227	000228	000229	000230	000231	000232	000233	000234	000235	000236	000237	000238	000239	000240	000241	000242	000243	000244	000245	000246	000247	000248	000249	000250	000251	000252	000253	000254	000255	000256	000257	000258	000259	000260	000261	000262	000263	000264	000265	000266	000267	000268	000269	000270	000271	000272	000273	000274	000275	000276	000277	000278	000279	000280	000281	000282	000283	000284	000285	000286	000287	000288	000289	000290	000291	000292	000293	000294	000295	000296	000297	000298	000299	000300	000301	000302	000303	000304	000305	000306	000307	000308	000309	000310	000311	000312	000313	000314	000315	000316	000317	000318	000319	000320	000321	000322	000323	000324	000325	000326	000327	000328	000329	000330	000331	000332	000333	000334	000335	000336	000337	000338	000339	000340	000341	000342	000343	000344	000345	000346	000347	000348	000349	000350	000351	000352	000353	000354	000355	000356	000357	000358	000359	000360	000361	000362	000363	000364	000365	000366	000367	000368	000369	000370	000371	000372	000373	000374	000375	000376	000377	000378	000379	000380	000381	000382	000383	000384	000385	000386	000387	000388	000389	000390	000391	000392	000393	000394	000395	000396	000397	000398	000399	000400	000401	000402	000403	000404	000405	000406	000407	000408	000409	000410	000411

LABEL	ISN	ADDR	LARFL	ISN	ADDR
6	13	0001C8	1	17	000230

LABEL	ISN	ADDR	LABEL	ISN	ADDR
000001	47	000000	000001	50	000000
000002	61	000000	000002	51	000000
000003	62	000000	000003	52	000000
000004	63	000000	000004	53	000000
000005	64	000000	000005	54	000000
000006	65	000000	000006	55	000000
000007	66	000000	000007	56	000000
000008	67	000000	000008	57	000000
000009	68	000000	000009	58	000000
000010	69	000000	000010	59	000000
000011	70	000000	000011	60	000000
000012	71	000000	000012	61	000000
000013	72	000000	000013	62	000000
000014	73	000000	000014	63	000000
000015	74	000000	000015	64	000000
000016	75	000000	000016	65	000000
000017	76	000000	000017	66	000000
000018	77	000000	000018	67	000000
000019	78	000000	000019	68	000000
000020	79	000000	000020	69	000000
000021	80	000000	000021	70	000000
000022	81	000000	000022	71	000000
000023	82	000000	000023	72	000000
000024	83	000000	000024	73	000000
000025	84	000000	000025	74	000000
000026	85	000000	000026	75	000000
000027	86	000000	000027	76	000000
000028	87	000000	000028	77	000000
000029	88	000000	000029	78	000000
000030	89	000000	000030	79	000000
000031	90	000000	000031	80	000000
000032	91	000000	000032	81	000000
000033	92	000000	000033	82	000000
000034	93	000000	000034	83	000000
000035	94	000000	000035	84	000000
000036	95	000000	000036	85	000000
000037	96	000000	000037	86	000000
000038	97	000000	000038	87	000000
000039	98	000000	000039	88	000000
000040	99	000000	000040	89	000000
000041	100	000000	000041	90	000000
000042	101	000000	000042	91	000000
000043	102	000000	000043	92	000000
000044	103	000000	000044	93	000000
000045	104	000000	000045	94	000000
000046	105	000000	000046	95	000000
000047	106	000000	000047	96	000000
000048	107	000000	000048	97	000000
000049	108	000000	000049	98	000000
000050	109	000000	000050	99	000000
000051	110	000000	000051	100	000000
000052	111	000000	000052	101	000000
000053	112	000000	000053	102	000000
000054	113	000000	000054	103	000000
000055	114	000000	000055	104	000000
000056	115	000000	000056	105	000000
000057	116	00000			

```

OPTIONS IN FFFCT*NAME(MAIN) OPTIMIZE(1) LINECOUNT(80) SIZE(MAX) AUTOOBL(NONE)

```

OPTIONS IN EFFECT SOURCE ERCDIC NOLIST NOCHECK OBJECT MAP NFORMAT NOGOSTMT XREF ALC NOANSF NOTERM IBM FLAG(1)

```

STATISTICS•
SOURCE STATEMENTS = 31, PROGRAM SIZE = 910, SUBPROGRAM NAME = RECT

```

STATISTICS • NO DIAGNOSTICS GENERATED

***** END OF COMPILATION *****

296K BYTES OF CORE NOT USED

•LEVEL 2.3.0 (JRMF 78)
***** END OF COMPILATION *****

SREV

05/360 FORTMAN H EXTENDED

DATE 01.141/14.21.07

PAGE 2

296K BYTES OF CORE NOT USED

PAGE IS
OF POOR QUALITY

ORIGINAL PAGE IS
OF POOR QUALITY

PAGE 4

LEVEL 2.3.0 (JOB 7H) DATE 01.130/13.30.32

ISN	ADDR	ISN	ADDR
00001	000720	15	0007AA
00002	000720	16	0007AA
00003	000720	17	0007AA
00004	000720	18	0007AA
00005	000720	19	0007AA
00006	000720	20	0007AA
00007	000720	21	0007AA
00008	000720	22	0007AA
00009	000720	23	0007AA
00010	000720	24	0007AA
00011	000720	25	0007AA
00012	000720	26	0007AA
00013	000720	27	0007AA
00014	000720	28	0007AA
00015	000720	29	0007AA
00016	000720	30	0007AA
00017	000720	31	0007AA
00018	000720	32	0007AA
00019	000720	33	0007AA
00020	000720	34	0007AA
00021	000720	35	0007AA
00022	000720	36	0007AA
00023	000720	37	0007AA
00024	000720	38	0007AA
00025	000720	39	0007AA
00026	000720	40	0007AA
00027	000720	41	0007AA
00028	000720	42	0007AA
00029	000720	43	0007AA
00030	000720	44	0007AA
00031	000720	45	0007AA
00032	000720	46	0007AA
00033	000720	47	0007AA
00034	000720	48	0007AA
00035	000720	49	0007AA
00036	000720	50	0007AA
00037	000720	51	0007AA
00038	000720	52	0007AA
00039	000720	53	0007AA
00040	000720	54	0007AA
00041	000720	55	0007AA
00042	000720	56	0007AA
00043	000720	57	0007AA
00044	000720	58	0007AA
00045	000720	59	0007AA
00046	000720	60	0007AA
00047	000720	61	0007AA
00048	000720	62	0007AA
00049	000720	63	0007AA
00050	000720	64	0007AA
00051	000720	65	0007AA
00052	000720	66	0007AA
00053	000720	67	0007AA
00054	000720	68	0007AA
00055	000720	69	0007AA
00056	000720	70	0007AA
00057	000720	71	0007AA
00058	000720	72	0007AA
00059	000720	73	0007AA
00060	000720	74	0007AA
00061	000720	75	0007AA
00062	000720	76	0007AA
00063	000720	77	0007AA
00064	000720	78	0007AA
00065	000720	79	0007AA
00066	000720	80	0007AA
00067	000720	81	0007AA
00068	000720	82	0007AA
00069	000720	83	0007AA
00070	000720	84	0007AA
00071	000720	85	0007AA
00072	000720	86	0007AA
00073	000720	87	0007AA
00074	000720	88	0007AA
00075	000720	89	0007AA
00076	000720	90	0007AA
00077	000720	91	0007AA
00078	000720	92	0007AA
00079	000720	93	0007AA
00080	000720	94	0007AA
00081	000720	95	0007AA
00082	000720	96	0007AA
00083	000720	97	0007AA
00084	000720	98	0007AA
00085	000720	99	0007AA
00086	000720	100	0007AA

FORMAT STATEMENT LABELS

OPTIONS IN EFFECT: NAME (MAIN) OPTIMIZE (1) LINE COUNT (NO) SIZE (MAX) AUTODIAG (NONE)

OPTIONS IN EFFECT: SOURCE FPCNIC POLIST NMODECK OBJECT MAP NINFORMAT NOGOSTMT THEF ALC NMANSE NOTERN THM FLAG (1)

STATISTICS* SOURCE STATISTICS = 66% PROGRAM SIZE = 338H, SURPHOGRAM NAME = TD.IRM

STATISTICS* NO DIAGNOSTICS GENERATED

***** END OF COMPIATION *****

272K BYTES OF CODE NOT USED

ORIGINAL PAGE IS
OF POOR QUALITY.

```

05LVEFL 23.0 (MIN 70) 1250VG 05/160 FOURMAN H EXTENDED DATE 01.139/13.23.63
  LABEL ISN ADDR LABEL ISN ADDR
  100001 05 00110 100002 10 0014C
  OPTIONS IN EFFECT NAME (MAIN) OPTIMIZE(1) LINK COMB(80) SIZE (MAX) AUTOINP (NONE)
  OPTIONS IN EFFECT SOURCE FCODE INCLIST NONECHK OBJECT MAP NORMAL NOGUSIMI XREF ALC HOANSF NOTERM INM FLAG(1)
  *STATISTICS* SOURCE STATISTICS = 20. PROGRAM SIZE = 742. SUBPROGRAM NAME = F2F.VG
  *STATISTICS* IN DIAGNOSTICS GENERATED
  ***** END OF COMPIATION *****
  292K BYTES OF CODE NOT USED

```


ORIGINAL PAGE IS
OF POOR QUALITY

*LFVEL 2.3.0 (JUN 74)
 10000 17 0001A
 *OPTIONS IN EFFECT: NAME (MAIN) OPTIMIZE (1) LINECOUNT (0) SIZE (MAX) AUTOMAP (NONE)
 *OPTIONS IN EFFECT: SOURCE EXECUTIVE NO. LIST NO. CHECK ON RECT MAP NO. WHAT INFORMATION 10000 0001A
 *STATISTICS: SOURCE STATEMENTS = 21. PROGRAM SIZE = 640. SUMMARY PROGRAM NAME = FCMISU
 *STATISTICS: NO DIAGNOSTICS GENERATED
 ***** END OF COMPILATION *****

DATE 01.130/13.23.95

PAGE 2

242K BYTES OF CODE NOT USED

LEVEL 2.3.0 (P. 74) 11001
STATISTICS AND DIAGNOSTICS GROUPED
***** END OF CO-ORDINATION *****

OS/360 PROGRAM EXTENSION

DATE 01.139/13.2%2%

PAGE 2

MARK ATTES OF CODE NOT USED

ORIGINAL PAGE IS
OF POOR QUALITY

APPENDIX E

ORIGINAL PAGE IS
OF POOR QUALITY

PAGE 001

FILE: CODE FILE A 1005 / PHONE UNIVERSITY

PROGRAM NUMBER:	123	74151	74233	74253
SPECIFIC NUMBER:	74197	74151	74233	74253
ACQUISITION:	U.S.	U.S.	U.S.	U.S.
SUBJECT:	2	2	2	2
LANDSAT NUMBER:	2	2	2	2

ORIGINAL PAGE IS
OF POOR QUALITY

CROP INFORMATION SUMMARY
TYPE DATA

CORN 12.00. 11.50. 1.15. 1.50
CROP
GREF
*END

SUPPORTING RESEARCH MULTITEMPORAL CLASSIFICATION

PROCESSING DATE - 05/21/81 AT 13: 0

SEGMENT NUMBER - 123 CROP OF INTEREST - CORN

PIXEL SKIP FACTOR = 1 LINE SKIP FACTOR = 3.1 (64.0 3.1) (60.0 8.0) (60.0 8.0)

TRAINING FIELD - LINE NO. SAMP. NO.
3.0 58.0
3.0 64.0
8.0 66.0
8.0 68.0

MEAN AND STD. DEV. FOR TRAINING FIELD BASED ON 10 PIXELS -

GREENS
NUMBER 78107 78161 78197 78233 78269

1 MEAN 12.12 11.00 50.02 47.33 19.30
STD. DEV. 1.10 1.01 4.31 2.40 1.73

CONSTANTS FOR MODEL -

CHANNEL NUMBER	A	ALPHA	BETA	TO	CHISO
INITIAL	12.00	11.50	1.15	1.50	
FINAL	11.84-- 0.00	19.94-- 0.00	2.10-- 0.00	1.61-- 0.00	2.07

PIXEL SKIP FACTOR = 1 LINE SKIP FACTOR = 1.1 (196.0 1.1) (196.0 117.0) (1.1 117.0)

VERT. SKIP FACTOR = 1.1 (196.0 1.1) (196.0 117.0) (1.1 117.0)

CLASSIFICATION FILE - RUN TIME: CP= 42.52 VIRTUAL CP= 41.65 IN MINUTES

DIFFERENCE IN INITIAL: ENDING CP TIMES IN HUNDREDTHS SECS.=255145
DIFFERENCE IN INITIAL: ENDING VIRTUAL TIMES IN HUNDREDTHS SECS.=249916

ORIGINAL PAGE IS
OF POOR QUALITY

ORIGINAL PAGE IS
OF POOR QUALITY

SUMMARY OF PROPS FOR THIS JOB ERROR NUMBER NUMBER OF ERRORS
207 3

BASA-50C